
Qtile Documentation

Release 0.18.1.dev0+g8e7ecc0.d20210704

Aldo Cortesi

Jul 04, 2021

CONTENTS

1	Getting started	1
2	Advanced scripting	101
3	Getting involved	119
4	Miscellaneous	127
5	How To	129
	Index	139

GETTING STARTED

1.1 Installing Qtile

1.1.1 Distro Guides

Below are the preferred installation methods for specific distros. If you are running something else, please see *Installing From Source*.

Installing on Arch Linux

Stable versions of Qtile are currently packaged for Arch Linux. To install this package, run:

```
pacman -S qtile
```

Please see the ArchWiki for more information on [Qtile](#).

Installing on Fedora

Stable versions of Qtile are currently packaged for current versions of Fedora. To install this package, run:

```
dnf -y install qtile
```

Installing on Funtoo

Latest versions of Qtile are available on Funtoo. To install it, run:

```
emerge -av x11-wm/qtile
```

You can also install the development version from GitHub:

```
echo "x11-wm/qtile-9999 **" >> /etc/portage/package.accept_keywords  
emerge -av qtile
```

Customize

You can customize your installation with the following useflags:

- dbus
- widget-khal-calendar
- widget-imap
- widget-keyboardkbdd
- widget-launchbar
- widget-mpd
- widget-mpris
- widget-wlan

The dbus useflag is enabled by default. Disable it only if you know what it is and know you don't use/need it.

All widget-* useflags are disabled by default because these widgets require additional dependencies while not everyone will use them. Enable only widgets you need to avoid extra dependencies thanks to these useflags.

Visit [Funtoo Qtile documentation](#) for more details on Qtile installation on Funtoo.

Installing on Debian or Ubuntu

Note: As of Ubuntu 20.04 (Focal Fossa), the package has been outdated and removed from the Ubuntu's official package list. Users are advised to follow the instructions of *Installing From Source*.

On other recent Ubuntu (17.04 or greater) and Debian unstable versions, there are Qtile packages available via:

```
sudo apt-get install qtile
```

On older versions of Ubuntu (15.10 to 16.10) and Debian 9, the dependencies are available via:

```
sudo apt-get install python3-xcffib python3-cairocffi
```

Installing on Slackware

Qtile is available on the [SlackBuilds.org](#) as:

Package Name	Description
qtile	stable branch (release)

Using slpkg (third party package manager)

The easy way to install Qtile is with `slpkg`. For example:

```
slpkg -s sbo qtile
```

Manual installation

Download dependencies first and install them. The order in which you need to install is:

- pycparser
- cffi
- futures
- python-xfib
- trollius
- cairocffi
- qtile

Please see the HOWTO for more information on [SlackBuild Usage HOWTO](#).

Installing on FreeBSD

Qtile is available via [FreeBSD Ports](#). It can be installed with

```
pkg install qtile
```

1.1.2 Installing From Source

First, you need to install all of Qtile's dependencies (although some are optional/not needed depending on your Python version, as noted below).

We aim to always support the last three versions of CPython, the reference Python interpreter. We usually support the latest stable version of [PyPy](#) as well. You can check the versions and interpreters we currently run our test suite against in our [tox configuration file](#).

There are not many differences between versions aside from Python features you may or may not be able to use in your config. PyPy should be faster at runtime than any corresponding CPython version under most circumstances, especially for bits of Python code that are run many times. CPython should start up faster than PyPy and has better compatibility for external libraries.

xcffib

Qtile uses [xcffib](#) as an XCB binding, which has its own instructions for building from source. However, if you'd like to skip building it, you can install its dependencies, you will need `libxcb` and `libffi` with the associated headers (`libxcb-render0-dev` and `libffi-dev` on Ubuntu), and install it via PyPI:

```
pip install xcffib
```

cairocffi

Qtile uses `cairocffi` with XCB support via `xcffib`. You'll need `libcairo2`, the underlying library used by the binding. You should **be sure before you install `cairocffi` that `xcffib` has been installed**, otherwise the needed `cairo-xcb` bindings will not be built. Once you've got the dependencies installed, you can use the latest version on PyPI:

```
pip install --no-cache-dir cairocffi
```

pangocairo

You'll also need `libpangocairo`, which on Ubuntu can be installed via `sudo apt-get install libpangocairo-1.0-0`. Qtile uses this to provide text rendering (and binds directly to it via `ffi` with a small in-tree binding).

dbus-next

Qtile uses `dbus-next` to interact with `dbus`. Qtile will run without this package but certain functionality will be lost (e.g. notifications).

You can install `dbus-next` from PyPI:

```
pip install dbus-next
```

Qtile

With the dependencies in place, you can now install `qtile`:

```
git clone git://github.com/qtile/qtile.git
cd qtile
pip install .
```

Stable versions of Qtile can be installed from PyPI:

```
pip install qtile
```

As long as the necessary libraries are in place, this can be done at any point, however, it is recommended that you first install `xcffib` to ensure the `cairo-xcb` bindings are built (see above).

Wayland

Qtile can also be run as a Wayland compositor rather than an X11 window manager. This does not require an X server or `xcffib` to be installed. Instead Qtile uses `pywlroots`, a Python binding around the `wlroots` library, both of which must be installed with the latest release. Be aware that some distributions package outdated versions of `wlroots`. `pywlroots` can be installed using `pip install` as above.

Qtile can then be run either from a TTY, or within an existing X11 or Wayland session where it will run inside a nested window:

```
qtile start -b wayland
```

If you want your config file to work with different backends but want some options set differently per backend, something like this may be useful:

```
from libqtile import qtile

if qtile.core.name == "x11":
    term = "urxvt"
elif qtile.core.name == "wayland":
    term = "foot"
```

1.2 Configuration

Qtile is configured in Python. A script (`~/.config/qtile/config.py` by default) is evaluated, and a small set of configuration variables are pulled from its global namespace.

1.2.1 Configuration lookup order

Qtile looks in the following places for a configuration file, in order:

- The location specified by the `-c` argument.
- `$XDG_CONFIG_HOME/qtile/config.py`, if it is set
- `~/.config/qtile/config.py`
- It reads the module `libqtile.resources.default_config`, included by default with every Qtile installation.

Qtile will try to create the configuration file as a copy of the default config, if it doesn't exist yet.

1.2.2 Default Configuration

The `default configuration` is invoked when qtile cannot find a configuration file. In addition, if qtile is restarted via `qshell`, qtile will load the default configuration if the config file it finds has some kind of error in it. The documentation below describes the configuration lookup process, as well as what the key bindings are in the default config.

The default config is not intended to be suitable for all users; it's mostly just there so qtile does `/something/` when fired up, and so that it doesn't crash and cause you to lose all your work if you reload a bad config.

Key Bindings

The `mod` key for the default config is `mod4`, which is typically bound to the “Super” keys, which are things like the windows key and the mac command key. The basic operation is:

- `mod + k` or `mod + j`: switch windows on the current stack
- `mod + <space>`: put focus on the other pane of the stack (when in stack layout)
- `mod + <tab>`: switch layouts
- `mod + w`: close window
- `mod + <ctrl> + r`: restart qtile with new config
- `mod + <group name>`: switch to that group
- `mod + <shift> + <group name>`: send a window to that group
- `mod + <enter>`: start terminal guessed by `libqtile.utils.guess_terminal`

- `mod + r`: start a little prompt in the bar so users can run arbitrary commands

The default config defines one screen and 8 groups, one for each letter in `asdfuiop`. It has a basic bottom bar that includes a group box, the current window name, a little text reminder that you're using the default config, a system tray, and a clock.

The default configuration has several more advanced key combinations, but the above should be enough for basic usage of qtile.

See *Keybindings in images* for visual keybindings in keyboard layout.

Mouse Bindings

By default, holding your mod key and clicking (and holding) a window will allow you to drag it around as a floating window.

1.2.3 Configuration variables

A Qtile configuration consists of a file with a bunch of variables in it, which qtile imports and then runs as a Python file to derive its final configuration. The documentation below describes the most common configuration variables; more advanced configuration can be found in the [qtile-examples](#) repository, which includes a number of real-world configurations that demonstrate how you can tune Qtile to your liking. (Feel free to issue a pull request to add your own configuration to the mix!)

Lazy objects

The `lazy.lazy` object is a special helper object to specify a command for later execution. This object acts like the root of the object graph, which means that we can specify a key binding command with the same syntax used to call the command through a script or through *qtile shell*.

Example

```
from libqtile.config import Key
from libqtile.command import lazy

keys = [
    Key(
        ["mod1"], "k",
        lazy.layout.down()
    ),
    Key(
        ["mod1"], "j",
        lazy.layout.up()
    )
]
```

Lazy functions

This is overview of the commonly used functions for the key bindings. These functions can be called from commands on the *Qtile* object or on another object in the command tree.

Some examples are given below.

General functions

function	description
lazy. spawn("application")	Run the application
lazy.spawncmd()	Open command prompt on the bar. See prompt widget.
lazy.restart()	Restart Qtile and reload its config. It won't close your windows
lazy.shutdown()	Close the whole Qtile

Group functions

function	description
lazy. next_layout()	Use next layout on the actual group
lazy. prev_layout()	Use previous layout on the actual group
lazy.screen. next_group()	Move to the group on the right
lazy.screen. prev_group()	Move to the group on the left
lazy.screen. toggle_group()	Move to the last visited group
lazy.group. next_window()	Switch window focus to next window in group
lazy.group. prev_window()	Switch window focus to previous window in group
lazy. group["group_name"]. toscreen()	Move to the group called <code>group_name</code> . Takes an optional <code>toggle</code> parameter (defaults to <code>True</code>). If this group is already on the screen, then the group is toggled with last used
lazy.layout. increase_ratio()	Increase the space for master window at the expense of slave windows
lazy.layout. decrease_ratio()	Decrease the space for master window in the advantage of slave windows

Window functions

function	description
lazy.window.kill()	Close the focused window
lazy.layout.next()	Switch window focus to other pane(s) of stack
lazy.window.togroup("group_name")	Move focused window to the group called <code>group_name</code>
lazy.window.toggle_floating()	Put the focused window to/from floating mode
lazy.window.toggle_fullscreen()	Put the focused window to/from fullscreen mode

ScratchPad DropDown functions

function	description
lazy.group["group_name"].dropdown_toggle("name")	Toggles the visibility of the specified DropDown window. On first use, the configured process is spawned.

User-defined functions

function	description
lazy.function(func, *args, **kwargs)	Calls <code>func(qtile, *args, **kwargs)</code> . NB. the <code>qtile</code> object is automatically passed as the first argument.

Groups

A group is a container for a bunch of windows, analogous to workspaces in other window managers. Each client window managed by the window manager belongs to exactly one group. The `groups` config file variable should be initialized to a list of `DGroup` objects.

`DGroup` objects provide several options for group configuration. Groups can be configured to show and hide themselves when they're not empty, spawn applications for them when they start, automatically acquire certain groups, and various other options.

Example

```

from libqtile.config import Group, Match
groups = [
    Group("a"),
    Group("b"),
    Group("c", matches=[Match(wm_class=["Firefox"])]),
]

# allow mod3+1 through mod3+0 to bind to groups; if you bind your groups
# by hand in your config, you don't need to do this.
from libqtile.dgroups import simple_key_binder
dgroups_key_binder = simple_key_binder("mod3")

```

Reference

Group

```

class libqtile.config.Group(name: str, matches: Optional[List[libqtile.config.Match]] = None,
                             exclusive=False, spawn: Optional[Union[str, List[str]]] = None, layout:
                             Optional[str] = None, layouts: Optional[List] = None, persist=True, init=True,
                             layout_opts=None, screen_affinity=None, position=9223372036854775807,
                             label: Optional[str] = None)

```

Represents a “dynamic” group

These groups can spawn apps, only allow certain Matched windows to be on them, hide when they’re not in use, etc. Groups are identified by their name.

Parameters

- name:** **string** the name of this group
- matches:** **default ``None``** list of `Match` objects whose windows will be assigned to this group
- exclusive:** **boolean** when other apps are started in this group, should we allow them here or not?
- spawn:** **string or list of strings** this will be `exec()` d when the group is created, you can pass either a program name or a list of programs to `exec()`
- layout:** **string** the name of default layout for this group (e.g. ‘max’ or ‘stack’). This is the name specified for a particular layout in `config.py` or if not defined it defaults in general the class name in all lower case.
- layouts:** **list** the group layouts list overriding global layouts. Use this to define a separate list of layouts for this particular group.
- persist:** **boolean** should this group stay alive with no member windows?
- init:** **boolean** is this group alive when qtile starts?
- position:** **int** group position
- label:** **string** the display name of the group. Use this to define a display name other than name of the group. If set to `None`, the display name is set to the name.

```

libqtile.dgroups.simple_key_binder(mod, keynames=None)
    Bind keys to mod+group position or to the keys specified as second argument

```

Group Matching

Match

```
class libqtile.config.Match(title=None, wm_class=None, role=None, wm_type=None,  
                             wm_instance_class=None, net_wm_pid=None, func:  
                             Optional[Callable[[Union[libqtile.backend.base.Window,  
libqtile.backend.base.Internal, libqtile.backend.base.Static]], bool]] = None)
```

Match for dynamic groups or auto-floating windows.

It can match by title, wm_class, role, wm_type, wm_instance_class or net_wm_pid.

Match supports both regular expression objects (i.e. the result of `re.compile()`) or strings (match as an “include”-match). If a window matches all specified values, it is considered a match.

Parameters

title: matches against the WM_NAME atom (X11) or title (Wayland)

wm_class: matches against the second string in WM_CLASS atom (X11) or app ID (Wayland)

role: matches against the WM_ROLE atom (X11 only)

wm_type: matches against the WM_TYPE atom (X11 only)

wm_instance_class: matches against the first string in WM_CLASS atom (X11) or app ID (Wayland)

net_wm_pid: matches against the _NET_WM_PID atom (X11) or PID (Wayland) - (only int allowed for this rule)

func: delegate the match to the given function, which receives the tested client as argument and must return True if it matches, False otherwise

Rule

```
class libqtile.config.Rule(match, group=None, float=False, intrusive=False, break_on_match=True)  
How to act on a match
```

A Rule contains a list of Match objects, and a specification about what to do when any of them is matched.

Parameters

match : Match object or a list of such associated with this Rule

float : auto float this window?

intrusive : override the group’s exclusive setting?

break_on_match : Should we stop applying rules if this rule is matched?

ScratchPad and DropDown

ScratchPad is a special - by default invisible - group which acts as a container for *DropDown* configurations. A *DropDown* can be configured to spawn a defined process and bind that process' window to it. The associated window can then be shown and hidden by the lazy command `dropdown_toggle()` (see *Lazy objects*) from the *ScratchPad* group. Thus - for example - your favorite terminal emulator turns into a quake-like terminal by the control of qtile.

If the *DropDown* window turns visible it is placed as a floating window on top of the current group. If the *DropDown* is hidden, it is simply switched back to the *ScratchPad* group.

Example

```
from libqtile.config import Group, ScratchPad, DropDown, Key
from libqtile.command import lazy
groups = [
    ScratchPad("scratchpad", [
        # define a drop down terminal.
        # it is placed in the upper third of screen by default.
        DropDown("term", "urxvt", opacity=0.8),

        # define another terminal exclusively for qshell at different position
        DropDown("qshell", "urxvt -hold -e qshell",
                 x=0.05, y=0.4, width=0.9, height=0.6, opacity=0.9,
                 on_focus_lost_hide=True) ]),
    Group("a"),
]

keys = [
    # toggle visibility of above defined DropDown named "term"
    Key([], 'F11', lazy.group['scratchpad'].dropdown_toggle('term')),
    Key([], 'F12', lazy.group['scratchpad'].dropdown_toggle('qshell')),
]
```

There is only one *DropDown* visible in current group at a time. If a further *DropDown* is set visible the currently shown *DropDown* turns invisible immediately.

Note that if the window is set to not floating, it is detached from *DropDown* and *ScratchPad*, and a new process is spawned next time the *DropDown* is set visible.

Reference

ScratchPad

class `libqtile.config.ScratchPad`(*name*, *dropdowns=None*, *position=9223372036854775807*, *label=""*)

Represents a “ScratchPad” group

ScratchPad adds a (by default) invisible group to qtile. That group is used as a place for currently not visible windows spawned by a *DropDown* configuration.

Parameters

name [string] the name of this group

dropdowns [default None] list of *DropDown* objects

position [int] group position

label [string] The display name of the ScratchPad group. Defaults to the empty string such that the group is hidden in GroupList widget.

DropDown

class `libqtile.config.DropDown(name, cmd, **config)`

Configure a specified command and its associated window for the ScratchPad. That window can be shown and hidden using a configurable keystroke or any other scripted trigger.

key	default	description
height	0.35	'Height of window as fraction of current screen.'
on_focus_lost_hide	True	'Shall the window be hidden if focus is lost? If so, the DropDown is hidden if window focus or the group is changed.'
opacity	0.9	'Opacity of window as fraction. Zero is opaque.'
warp_pointer	True	'Shall pointer warp to center of window on activation? This has only effect if any of the on_focus_lost_xxx configurations is True'
width	0.8	'Width of window as fraction of current screen width'
x	0.1	'X position of window as fraction of current screen width. 0 is the left most position.'
y	0.0	'Y position of window as fraction of current screen height. 0 is the top most position. To show the window at bottom, you have to configure a value < 1 and an appropriate height.'

Keys

The keys variable defines Qtile's key bindings. Individual key bindings are defined with `libqtile.config.Key` as demonstrated in the following example. Note that you may specify more than one callback functions.

```
from libqtile.config import Key

keys = [
    # Pressing "Meta + Shift + a".
    Key(["mod4", "shift", "a", callback, ...),

    # Pressing "Control + p".
    Key(["control", "p", callback, ...),

    # Pressing "Meta + Tab".
    Key(["mod4", "mod1", "Tab", callback, ...),
]
```

The above may also be written more concisely with the help of the `libqtile.config.EzKey` helper class. The following example is functionally equivalent to the above:

```
from libqtile.config import EzKey as Key

keys = [
    Key("M-S-a", callback, ...),
    Key("C-p", callback, ...),
```

(continues on next page)

(continued from previous page)

```
Key("M-A-<Tab>", callback, ...),
]
```

The EzKey modifier keys (i.e. MASC) can be overwritten through the `EzKey.modifier_keys` dictionary. The defaults are:

```
modifier_keys = {
    'M': 'mod4',
    'A': 'mod1',
    'S': 'shift',
    'C': 'control',
}
```

Callbacks can also be configured to work only under certain conditions by using the `when()` method. Currently, two conditions are supported:

```
from libqtile.config import Key

keys = [
    # Only trigger callback for a specific layout
    Key(
        [mod, 'shift'],
        "j",
        lazy.layout.grow().when(layout='verticaltile'),
        lazy.layout.grow_down().when(layout='columns')
    ),

    # Limit action to when the current window is not floating (default True)
    Key([mod], "f", lazy.window.toggle_fullscreen().when(when_floating=False))
]
```

KeyChords

Qtile also allows sequences of keys to trigger callbacks. In Qtile, these sequences are known as chords and are defined with `libqtile.config.KeyChord`. Chords are added to the `keys` section of the config file.

```
from libqtile.config import Key, KeyChord

keys = [
    KeyChord([mod], "z", [
        Key([], "x", lazy.spawn("xterm"))
    ])
]
```

The above code will launch `xterm` when the user presses `Mod + z`, followed by `x`.

Warning: Users should note that key chords are aborted by pressing `<escape>`. In the above example, if the user presses `Mod + z`, any following key presses will still be sent to the currently focussed window. If `<escape>` has not been pressed, the next press of `x` will launch `xterm`.

Modes

Chords can optionally specify a “mode”. When this is done, the mode will remain active until the user presses <escape>. This can be useful for configuring a subset of commands for a particular situations (i.e. similar to vim modes).

```
from libqtile.config import Key, KeyChord

keys = [
    KeyChord([mod], "z", [
        Key([], "g", lazy.layout.grow()),
        Key([], "s", lazy.layout.shrink()),
        Key([], "n", lazy.layout.normalize()),
        Key([], "m", lazy.layout.maximize()),
        mode="Windows"
    ])
]
```

In the above example, pressing Mod + z triggers the “Windows” mode. Users can then resize windows by just pressing g (to grow the window), s to shrink it etc. as many times as needed. To exit the mode, press <escape>.

Note: If using modes, users may also wish to use the Chord widget (*libqtile.widget.chord.Chord*) as this will display the name of the currently active mode on the bar.

Chains

Chords can also be chained to make even longer sequences.

```
from libqtile.config import Key, KeyChord

keys = [
    KeyChord([mod], "z", [
        KeyChord([], "x", [
            Key([], "c", lazy.spawn("xterm"))
        ])
    ])
]
```

Modes can also be added to chains if required. The following example demonstrates the behaviour when using the mode argument in chains:

```
from libqtile.config import Key, KeyChord

keys = [
    KeyChord([mod], "z", [
        KeyChord([], "y", [
            KeyChord([], "x", [
                Key([], "c", lazy.spawn("xterm"))
            ], mode="inner")
        ])
    ], mode="outer")
]
```

After pressing `Mod+z x c`, the “inner” mode will remain active. When pressing `<escape>`, the “inner” mode is exited. Since the mode in between does not have `mode set`, it is also left. Arriving at the “outer” mode (which has this argument set) stops the “leave” action and “outer” now becomes the active mode.

Note: If you want to bind a custom key to leave the current mode (e.g. `Control + G` in addition to `<escape>`), you can specify `lazy.ungrab_chord()` as the key action. To leave all modes and return to the root bindings, use `lazy.ungrab_all_chords()`.

Modifiers

On most systems `mod1` is the `Alt` key - you can see which modifiers, which are enclosed in a list, map to which keys on your system by running the `xmodmap` command. This example binds `Alt-k` to the “down” command on the current layout. This command is standard on all the included layouts, and switches to the next window (where “next” is defined differently in different layouts). The matching “up” command switches to the previous window.

Modifiers include: “shift”, “lock”, “control”, “mod1”, “mod2”, “mod3”, “mod4”, and “mod5”. They can be used in combination by appending more than one modifier to the list:

```
Key(
    ["mod1", "control"], "k",
    lazy.layout.shuffle_down()
)
```

Special keys

These are most commonly used special keys. For complete list please see [the code](#). You can create bindings on them just like for the regular keys. For example `Key(["mod1"], "F4", lazy.window.kill())`.

Return
BackSpace
Tab
space
Home, End
Left, Up, Right, Down
F1, F2, F3, ...
XF86AudioRaiseVolume
XF86AudioLowerVolume
XF86AudioMute
XF86AudioNext
XF86AudioPrev
XF86MonBrightnessUp
XF86MonBrightnessDown

Reference

Key

class libqtile.config.**Key**(*modifiers: List[str], key: str, *commands, desc: str = ""*)

Defines a keybinding.

Parameters

modifiers: A list of modifier specifications. Modifier specifications are one of: “shift”, “lock”, “control”, “mod1”, “mod2”, “mod3”, “mod4”, “mod5”.

key: A key specification, e.g. “a”, “Tab”, “Return”, “space”.

commands: A list of lazy command objects generated with the lazy.lazy helper. If multiple Call objects are specified, they are run in sequence.

desc: description to be added to the key binding

KeyChord

class libqtile.config.**KeyChord**(*modifiers: List[str], key: str, submappings: List[Union[libqtile.config.Key, libqtile.config.KeyChord]], mode: str = ""*)

Define a key chord aka vim like mode

Parameters

modifiers: A list of modifier specifications. Modifier specifications are one of: “shift”, “lock”, “control”, “mod1”, “mod2”, “mod3”, “mod4”, “mod5”.

key: A key specification, e.g. “a”, “Tab”, “Return”, “space”.

submappings: A list of Key or KeyChord declarations to bind in this chord.

mode: A string with vim like mode name. If it’s set, the chord mode will not be left after a keystroke (except for Esc which always leaves the current chord/mode).

EzConfig

class libqtile.config.**EzConfig**

Helper class for defining key and button bindings in an emacs-like format. Inspired by Xmonad’s XMonad.Util.EZConfig.

Layouts

A layout is an algorithm for laying out windows in a group on your screen. Since Qtile is a tiling window manager, this usually means that we try to use space as efficiently as possible, and give the user ample commands that can be bound to keys to interact with layouts.

The `layouts` variable defines the list of layouts you will use with Qtile. The first layout in the list is the default. If you define more than one layout, you will probably also want to define key bindings to let you switch to the next and previous layouts.

See *Built-in Layouts* for a listing of available layouts.

Example

```
from libqtile import layout
layouts = [
    layout.Max(),
    layout.Stack(stacks=2)
]
```

Mouse

The mouse config file variable defines a set of global mouse actions, and is a list of *Click* and *Drag* objects, which define what to do when a window is clicked or dragged.

Example

```
from libqtile.config import Click, Drag
mouse = [
    Drag([mod], "Button1", lazy.window.set_position_floating(),
        start=lazy.window.get_position()),
    Drag([mod], "Button3", lazy.window.set_size_floating(),
        start=lazy.window.get_size()),
    Click([mod], "Button2", lazy.window.bring_to_front())
]
```

The above example can also be written more concisely with the help of the *EzClick* and *EzDrag* helpers:

```
from libqtile.config import EzClick as Click, EzDrag as Drag
mouse = [
    Drag("M-1", lazy.window.set_position_floating(),
        start=lazy.window.get_position()),
    Drag("M-3", lazy.window.set_size_floating(),
        start=lazy.window.get_size()),
    Click("M-2", lazy.window.bring_to_front())
]
```

Reference

Click

class libqtile.config.Click(modifiers: List[str], button: str, *commands, **kwargs)
 Defines binding of a mouse click

Drag

`class libqtile.config.Drag(*args, start=False, **kwargs)`

Defines binding of a mouse to some dragging action

On each motion event command is executed with two extra parameters added x and y offset from previous move.

Screens

The screens configuration variable is where the physical screens, their associated bars, and the widgets contained within the bars are defined.

See *Built-in Widgets* for a listing of available widgets.

Example

Tying together screens, bars and widgets, we get something like this:

```
from libqtile.config import Screen
from libqtile import bar, widget

screens = [
    Screen(
        bottom=bar.Bar([
            widget.GroupBox(),
            widget.WindowName()
        ], 30),
    ),
    Screen(
        bottom=bar.Bar([
            widget.GroupBox(),
            widget.WindowName()
        ], 30),
    )
]
```

Bars support both solid background colors and gradients by supplying a list of colors that make up a linear gradient. For example, `bar.Bar(..., background="#000000")` will give you a black background (the default), while `bar.Bar(..., background=["#000000", "#FFFFFF"])` will give you a background that fades from black to white.

Bars (and widgets) also support transparency by adding an alpha value to the desired color. For example, `bar.Bar(..., background="#00000000")` will result in a fully transparent bar. Widget contents will not be impacted i.e. this is different to the `opacity` parameter which sets the transparency of the entire window.

Note: In X11 backends, transparency will be disabled in a bar if the background color is fully opaque.

Fake Screens

instead of using the variable `screens` the variable `fake_screens` can be used to set split a physical monitor into multiple screens. They can be used like this:

```

from libqtile.config import Screen
from libqtile import bar, widget

# screens look like this
#      600      300
# |-----|-----|
# |           480|   |580
# |  A           | B |
# |-----|---|   |
# |           400|---|
# |  C           |   |400
# |-----|   D   |
#      500   |-----|
#
#           400
#
# Notice there is a hole in the middle
# also D goes down below the others

fake_screens = [
    Screen(
        bottom=bar.Bar(
            [
                widget.Prompt(),
                widget.Sep(),
                widget.WindowName(),
                widget.Sep(),
                widget.Systray(),
                widget.Sep(),
                widget.Clock(format='%H:%M:%S %d.%m.%Y')
            ],
            24,
            background="#555555"
        ),
        x=0,
        y=0,
        width=600,
        height=480
    ),
    Screen(
        top=bar.Bar(
            [
                widget.GroupBox(),
                widget.WindowName(),
                widget.Clock()
            ],
            30,
        ),
        x=600,

```

(continues on next page)

(continued from previous page)

```
        y=0,
        width=300,
        height=580
    ),
    Screen(
        top=bar.Bar(
            [
                widget.GroupBox(),
                widget.WindowName(),
                widget.Clock()
            ],
            30,
        ),
        x=0,
        y=480,
        width=500,
        height=400
    ),
    Screen(
        top=bar.Bar(
            [
                widget.GroupBox(),
                widget.WindowName(),
                widget.Clock()
            ],
            30,
        ),
        x=500,
        y=580,
        width=400,
        height=400
    ),
]
```

Third-party bars

There might be some reasons to use third-party bars. For instance you can come from another window manager and you have already configured dzen2, xmbar, or something else. They definitely can be used with Qtile too. In fact, any additional configurations aren't needed. Just run the bar and qtile will adapt.

Reference

Screen

```
class libqtile.config.Screen(top: Optional[Union[libqtile.bar.Bar, libqtile.bar.Gap]] = None, bottom:
    Optional[Union[libqtile.bar.Bar, libqtile.bar.Gap]] = None, left:
    Optional[Union[libqtile.bar.Bar, libqtile.bar.Gap]] = None, right:
    Optional[Union[libqtile.bar.Bar, libqtile.bar.Gap]] = None, wallpaper:
    Optional[str] = None, wallpaper_mode: Optional[str] = None, x:
    Optional[int] = None, y: Optional[int] = None, width: Optional[int] = None,
    height: Optional[int] = None)
```

A physical screen, and its associated paraphernalia.

Define a screen with a given set of Bars of a specific geometry. Note that `bar.Bar` objects can only be placed at the top or the bottom of the screen (`bar.Gap` objects can be placed anywhere). Also, `x`, `y`, `width`, and `height` aren't specified usually unless you are using 'fake screens'.

The `wallpaper` parameter, if given, should be a path to an image file. How this image is painted to the screen is specified by the `wallpaper_mode` parameter. By default, the image will be placed at the screens origin and retain its own dimensions. If the mode is 'fill', the image will be centred on the screen and resized to fill it. If the mode is 'stretch', the image is stretched to fit all of it into the screen.

Bar

```
class libqtile.bar.Bar(widgets, size, **config)
```

A bar, which can contain widgets

Parameters

widgets : A list of widget objects.

size : The "thickness" of the bar, i.e. the height of a horizontal bar, or the width of a vertical bar.

key	default	description
background	'#000000'	'Background colour.'
margin	0	'Space around bar as int or list of ints [N E S W].'
opacity	1	'Bar window opacity.'

Gap

```
class libqtile.bar.Gap(size)
```

A gap placed along one of the edges of the screen

If a gap has been defined, Qtile will avoid covering it with windows. The most probable reason for configuring a gap is to make space for a third-party bar or other static window.

Parameters

size : The "thickness" of the gap, i.e. the height of a horizontal gap, or the width of a vertical gap.

Hooks

Qtile provides a mechanism for subscribing to certain events in `libqtile.hook`. To subscribe to a hook in your configuration, simply decorate a function with the hook you wish to subscribe to.

See *Built-in Hooks* for a listing of available hooks.

Examples

Automatic floating dialogs

Let's say we wanted to automatically float all dialog windows (this code is not actually necessary; Qtile floats all dialogs by default). We would subscribe to the `client_new` hook to tell us when a new window has opened and, if the type is "dialog", as can set the window to float. In our configuration file it would look something like this:

```
from libqtile import hook

@hook.subscribe.client_new
def floating_dialogs(window):
    dialog = window.window.get_wm_type() == 'dialog'
    transient = window.window.get_wm_transient_for()
    if dialog or transient:
        window.floating = True
```

A list of available hooks can be found in the *Built-in Hooks* reference.

Autostart

If you want to run commands or spawn some applications when Qtile starts, you'll want to look at the `startup` and `startup_once` hooks. `startup` is emitted every time Qtile starts (including restarts), whereas `startup_once` is only emitted on the very first startup.

Let's create an executable file `~/config/qtile/autostart.sh` that will start a few programs when Qtile first runs. Remember to `chmod +x` this file so that it can be executed.

```
#!/bin/sh
pidgin &
dropbox start &
```

We can then subscribe to `startup_once` to run this script:

```
import os
import subprocess

@hook.subscribe.startup_once
def autostart():
    home = os.path.expanduser('~/.config/qtile/autostart.sh')
    subprocess.call([home])
```

Accessing the qtile object

If you want to do something with the Qtile manager instance inside a hook, it can be imported into your config:

```
from libqtile import qtile
```

In addition to the above variables, there are several other boolean configuration variables that control specific aspects of Qtile’s behavior:

variable	default	description
auto_fullscreen	True	If a window requests to be fullscreen, it is automatically fullscreened. Set this to false if you only want windows to be fullscreen if you ask them to be.
bring_front_click	False	When clicked, should the window be brought to the front or not. If this is set to “floating_only”, only floating windows will get affected (This sets the X Stack Mode to Above.)
cursor_warp	False	If true, the cursor follows the focus as directed by the keyboard, warping to the center of the focused window. When switching focus between screens, If there are no windows in the screen, the cursor will warp to the center of the screen.
dgroups_key_binder	None	A function which generates group binding hotkeys. It takes a single argument, the DGroups object, and can use that to set up dynamic key bindings. A sample implementation is available in libqtile/dgroups.py called <code>simple_key_binder()</code> , which will bind groups to <code>mod+shift+0-10</code> by default.
dgroups_app_rules		A list of Rule objects which can send windows to various groups based on matching criteria.
extension_defaults	same as <code>wid- get_defaults</code>	Default settings for extensions.
floating_layout	layout.Floating(toggles_if_unfocused)	The default floating layout to use. This allows you to set custom floating rules among other things. See the configuration file for the default <code>float_rules</code> .
focus_on_window_activation	smart	Behavior of the <code>_NET_ACTIVATE_WINDOW</code> message sent by applications <ul style="list-style-type: none"> urgent: urgent flag is set for the window focus: automatically focus the window smart: automatically focus if the window is in the current group never: never automatically focus any window that requests it
follow_mouse_focus	True	Controls whether or not focus follows the mouse around as it moves across windows in a layout.
wid- get_defaults	<code>dict(font='sans', font-size=12, padding=3)</code>	Default settings for bar widgets.
re- config- ure_screens	True	Controls whether or not to automatically reconfigure screens when there are changes in randr output configuration.
wm- name	“LG3D”	Gasp! We’re lying here. In fact, nobody really uses or cares about this string besides java UI toolkits; you can see several discussions on the mailing lists, GitHub issues, and other WM documentation that suggest setting this string if your java app doesn’t work correctly. We may as well just lie and say that we’re a working one by default. We choose LG3D to maximize irony: it is a 3D non-reparenting WM written in java that happens to be on java’s whitelist.
auto_minimize	True	If things like steam games want to auto-minimize themselves when losing focus, should we respect this or not?

1.2.4 Testing your configuration

The best way to test changes to your configuration is with the provided Xephyr script. This will run Qtile with your `config.py` inside a nested X server and prevent your running instance of Qtile from crashing if something goes wrong.

See *Hacking Qtile* for more information on using Xephyr.

1.2.5 Starting Qtile

There are several ways to start Qtile. The most common way is via an entry in your X session manager's menu. The default Qtile behavior can be invoked by creating a `qtile.desktop` file in `/usr/share/xsessions`.

A second way to start Qtile is a custom X session. This way allows you to invoke Qtile with custom arguments, and also allows you to do any setup you want (e.g. special keyboard bindings like mapping caps lock to control, setting your desktop background, etc.) before Qtile starts. If you're using an X session manager, you still may need to create a `custom.desktop` file similar to the `qtile.desktop` file above, but with `Exec=/etc/X11/xsession`. Then, create your own `~/.xsession`. There are several examples of user defined `xsession`s in the `qtile-examples` repository.

If there is no display manager such as SDDM, LightDM or other and there is need to start Qtile directly from `~/.xinitrc` do that by adding `exec qtile` at the end.

In very special cases, ex. Qtile crashing during session, then suggestion would be to start through a loop to save running applications:

```
while true; do
    qtile
done
```

Finally, if you're a gnome user, you can start integrate Qtile into Gnome's session manager and use gnome as usual.

Running from systemd

This case will cover automatic login to Qtile after booting the system without using display manager. It logs in virtual console and init X by running through session.

Automatic login to virtual console

To get login into virtual console as an example edit `getty` service by running `systemctl edit getty@tty1` and add instructions to `/etc/systemd/system/getty@tty1.service.d/override.conf`:

```
[Service]
ExecStart=
ExecStart=-/usr/bin/agetty --autologin username --noclear %I $TERM
```

`username` should be changed to current user name.

Check more for other [examples](#).

Autostart X session

After login X session should be started. That can be done by `.bash_profile` if bash is used or `.zprofile` in case of zsh. Other shells can be adjusted by given examples.

```
if systemctl -q is-active graphical.target && [[ ! $DISPLAY && $XDG_VTNR -eq 1 ]]; then
    exec startx
fi
```

And to start Qtile itself `.xinitrc` should be fixed:

```
# some apps that should be started before Qtile, ex.
#
# [[ -f ~/.Xresources ]] && xrdp -merge ~/.Xresources
# ~/.fehbg &
# nm-applet &
# blueman-applet &
# dunst &
#
# or
#
# source ~/.xsession

exec qtile start
```

Running Inside Gnome

Add the following snippet to your Qtile configuration. As per [this page](#), it registers Qtile with gnome-session. Without it, a “Something has gone wrong!” message shows up a short while after logging in. `dbus-send` must be on your `$PATH`.

```
import subprocess
import os
from libqtile import hook

@hook.subscribe.startup
def dbus_register():
    id = os.environ.get('DESKTOP_AUTOSTART_ID')
    if not id:
        return
    subprocess.Popen(['dbus-send',
                      '--session',
                      '--print-reply',
                      '--dest=org.gnome.SessionManager',
                      '/org/gnome/SessionManager',
                      'org.gnome.SessionManager.RegisterClient',
                      'string:qtile',
                      'string:' + id])
```

This adds a new entry “Qtile GNOME” to GDM’s login screen.

```
$ cat /usr/share/xsessions/qtile_gnome.desktop
[Desktop Entry]
```

(continues on next page)

(continued from previous page)

```
Name=Qtile GNOME
Comment=Tiling window manager
TryExec=/usr/bin/gnome-session
Exec=gnome-session --session=qtile
Type=XSession
```

The custom session for gnome-session.

For Gnome >= 3.23.2 (Ubuntu >= 17.04, Fedora >= 26, etc.)

```
$ cat /usr/share/gnome-session/sessions/qtile.session
[GNOME Session]
Name=Qtile session
RequiredComponents=qtile;org.gnome.SettingsDaemon.AllySettings;org.gnome.SettingsDaemon.
↳Clipboard;org.gnome.SettingsDaemon.Color;org.gnome.SettingsDaemon.Datetime;org.gnome.
↳SettingsDaemon.Housekeeping;org.gnome.SettingsDaemon.Keyboard;org.gnome.SettingsDaemon.
↳MediaKeys;org.gnome.SettingsDaemon.Mouse;org.gnome.SettingsDaemon.Power;org.gnome.
↳SettingsDaemon.PrintNotifications;org.gnome.SettingsDaemon.Rfkill;org.gnome.
↳SettingsDaemon.ScreensaverProxy;org.gnome.SettingsDaemon.Sharing;org.gnome.
↳SettingsDaemon.Smartcard;org.gnome.SettingsDaemon.Sound;org.gnome.SettingsDaemon.Wacom;
↳org.gnome.SettingsDaemon.XSettings;
```

Or for older Gnome versions

```
$ cat /usr/share/gnome-session/sessions/qtile.session
[GNOME Session]
Name=Qtile session
RequiredComponents=qtile;gnome-settings-daemon;
```

So that Qtile starts automatically on login.

```
$ cat /usr/share/applications/qtile.desktop
[Desktop Entry]
Type=Application
Encoding=UTF-8
Name=Qtile
Exec=qtile start
NoDisplay=true
X-GNOME-WMName=Qtile
X-GNOME-Autostart-Phase=WindowManager
X-GNOME-Provides=windowmanager
X-GNOME-Autostart-Notify=false
```

The above does not start gnome-panel. Getting gnome-panel to work requires some extra Qtile configuration, mainly making the top and bottom panels static on panel startup and leaving a gap at the top (and bottom) for the panel window.

You might want to add keybindings to log out of the GNOME session.

```
Key([mod, 'control'], 'l', lazy.spawn('gnome-screensaver-command -l')),
Key([mod, 'control'], 'q', lazy.spawn('gnome-session-quit --logout --no-prompt')),
Key([mod, 'shift', 'control'], 'q', lazy.spawn('gnome-session-quit --power-off')),
```

The above apps need to be in your path (though they are typically installed in /usr/bin, so they probably are if they're installed at all).

1.3 Troubleshooting

1.3.1 So something has gone wrong... what do you do?

When Qtile is running, it logs error messages (and other messages) to its log file. This is found at `~/.local/share/qtile/qtile.log`. This is the first place to check to see what is going on. If you are getting unexpected errors from normal usage or your configuration (and you're not doing something wacky) and believe you have found a bug, then please *report a bug*.

If you are *hacking on Qtile* and you want to debug your changes, this log is your best friend. You can send messages to the log from within libqtile by using the logger:

```
from libqtile.log_utils import logger

logger.warning("Your message here")
logger.warning(variable_you_want_to_print)

try:
    # some changes here that might error
    raise Exception as e:
    logger.exception(e)
```

`logger.warning` is convenient because its messages will always be visible in the log. `logger.exception` is helpful because it will print the full traceback of an error to the log. By sticking these amongst your changes you can look more closely at the effects of any changes you made to Qtile's internals.

1.3.2 Capturing an xtrace

Occasionally, a bug will be low level enough to require an `xtrace` of Qtile's conversations with the X server. To capture one of these, create an `xinitrc` or similar file with:

```
exec xtrace qtile >> ~/qtile.log
```

This will put the `xtrace` output in Qtile's logfile as well. You can then demonstrate the bug, and paste the contents of this file into the bug report.

Note that `xtrace` may be named `x11trace` on some platforms, for example, on Fedora.

1.4 Shell commands

qtile uses a subcommand structure; various subcommands are listed below. Additionally, two other commands available in the `scripts/` section of the repository are also documented below.

1.4.1 qtile start

This is the entry point for the window manager, and what you should run from your `.xsession` or similar. This will make an attempt to detect if qtile is already running and fail if it is. See `qtile start --help` for more details.

1.4.2 qtile shell

The Qtile command shell is a command-line shell interface that provides access to the full complement of Qtile command functions. The shell features command name completion, and full command documentation can be accessed from the shell itself. The shell uses GNU Readline when it's available, so the interface can be configured to, for example, obey VI keybindings with an appropriate `.inputrc` file. See the GNU Readline documentation for more information.

Navigating the Object Graph

The shell presents a filesystem-like interface to the object graph - the builtin “`cd`” and “`ls`” commands act like their familiar shell counterparts:

```
> ls
layout/  widget/  screen/  bar/      window/  group/

> cd bar

bar> ls
bottom/

bar> cd bottom

bar['bottom']> ls
screen/

bar['bottom']> cd ../../

> ls
layout/  widget/  screen/  bar/      window/  group/
```

Note that the shell provides a “short-hand” for specifying node keys (as opposed to children). The following is a valid shell path:

```
> cd group/4/window/31457314
```

The command prompt will, however, always display the Python node path that should be used in scripts and key bindings:

```
group['4'].window[31457314]>
```

Live Documentation

The shell `help` command provides the canonical documentation for the Qtile API:

```
> cd layout/1

layout[1]> help
help command  -- Help for a specific command.

Builtins
=====
cd  exit help ls  q  quit

Commands for this object
=====
add          commands  current  delete  doc
down        get_info  items   next    previous
rotate      shuffle_down shuffle_up toggle_split up

layout[1]> help previous
previous()
Focus previous stack.
```

1.4.3 qtile cmd-obj

This is a simple tool to expose `qtile.command` functionality to shell. This can be used standalone or in other shell scripts.

Examples:

Output of `qtile cmd-obj -h`

```
usage: qtile cmd-obj [-h] [--object OBJ_SPEC [OBJ_SPEC ...]]
                  [--function FUNCTION] [--args ARGS [ARGS ...]] [--info]

Simple tool to expose qtile.command functionality to shell.

optional arguments:
  -h, --help            show this help message and exit
  --object OBJ_SPEC [OBJ_SPEC ...], -o OBJ_SPEC [OBJ_SPEC ...]
                        Specify path to object (space separated). If no
                        --function flag display available commands.
  --function FUNCTION, -f FUNCTION
                        Select function to execute.
  --args ARGS [ARGS ...], -a ARGS [ARGS ...]
                        Set arguments supplied to function.
  --info, -i            With both --object and --function args prints
                        documentation for function.

Examples:
qtile cmd-obj
```

(continues on next page)

(continued from previous page)

```

qtile cmd-obj -o cmd
qtile cmd-obj -o cmd -f prev_layout -i
qtile cmd-obj -o cmd -f prev_layout -a 3 # prev_layout on group 3
qtile cmd-obj -o group 3 -f focus_back

```

Output of `qtile cmd-obj -o group 3`

```

-o group 3 -f commands           Returns a list of possible commands for this object
-o group 3 -f doc                * Returns the documentation for a specified command name
-o group 3 -f eval              * Evaluates code in the same context as this function
-o group 3 -f focus_back        Focus the window that had focus before the current one.
↳got it.
-o group 3 -f focus_by_name     * Focus the first window with the given name. Do nothing.
↳if the name is
-o group 3 -f function          * Call a function with current object as argument
-o group 3 -f info              Returns a dictionary of info for this group
-o group 3 -f info_by_name     * Get the info for the first window with the given name.
↳without giving it
-o group 3 -f items            * Returns a list of contained items for the specified.
↳name
-o group 3 -f next_window       Focus the next window in group.
-o group 3 -f prev_window       Focus the previous window in group.
-o group 3 -f set_label        * Set the display name of current group to be used in.
↳GroupBox widget.
-o group 3 -f setlayout
-o group 3 -f switch_groups     * Switch position of current group with name
-o group 3 -f toscreen         * Pull a group to a specified screen.
-o group 3 -f unminimize_all    Unminimise all windows in this group

```

Output of `qtile cmd-obj -o cmd`

```

-o cmd -f add_rule              * Add a dgroup rule, returns rule_id needed to remove it
-o cmd -f addgroup             * Add a group with the given name
-o cmd -f commands            Returns a list of possible commands for this object
-o cmd -f critical             Set log level to CRITICAL
-o cmd -f debug                Set log level to DEBUG
-o cmd -f delgroup            * Delete a group with the given name
-o cmd -f display_kb          * Display table of key bindings
-o cmd -f doc                  * Returns the documentation for a specified command name
-o cmd -f error                Set log level to ERROR
-o cmd -f eval                 * Evaluates code in the same context as this function
-o cmd -f findwindow          * Launch prompt widget to find a window of the given name
-o cmd -f focus_by_click      * Bring a window to the front
-o cmd -f function            * Call a function with current object as argument
-o cmd -f get_info            Prints info for all groups
-o cmd -f get_state           Get pickled state for restarting qtile
-o cmd -f get_test_data       Returns any content arbitrarily set in the self.test_
↳data attribute.

```

(continues on next page)

(continued from previous page)

```

-o cmd -f groups          Return a dictionary containing information for all
↳groups
-o cmd -f hide_show_bar  * Toggle visibility of a given bar
-o cmd -f info           Set log level to INFO
-o cmd -f internal_windows Return info for each internal window (bars, for
↳example)
-o cmd -f items          * Returns a list of contained items for the specified
↳name
-o cmd -f list_widgets   List of all addressible widget names
-o cmd -f next_layout    * Switch to the next layout.
-o cmd -f next_screen    Move to next screen
-o cmd -f next_urgent    Focus next window with urgent hint
-o cmd -f pause          Drops into pdb
-o cmd -f prev_layout    * Switch to the previous layout.
-o cmd -f prev_screen    Move to the previous screen
-o cmd -f qtile_info     Returns a dictionary of info on the Qtile instance
-o cmd -f qtilecmd       * Execute a Qtile command using the client syntax
-o cmd -f remove_rule    * Remove a dgroup rule by rule_id
-o cmd -f restart        Restart qtile
-o cmd -f run_extension  * Run extensions
-o cmd -f run_extention  * Deprecated alias for cmd_run_extension()
-o cmd -f run_external   * Run external Python script
-o cmd -f screens        Return a list of dictionaries providing information on
↳all screens
-o cmd -f shutdown       Quit Qtile
-o cmd -f simulate_keypress * Simulates a keypress on the focused window.
-o cmd -f spawn          * Run cmd in a shell.
-o cmd -f spawncmd       * Spawn a command using a prompt widget, with tab-
↳completion.
-o cmd -f status         Return "OK" if Qtile is running
-o cmd -f switch_groups  * Switch position of groupa to groupb
-o cmd -f switchgroup    * Launch prompt widget to switch to a given group to the
↳current screen
-o cmd -f sync           Sync the X display. Should only be used for development
-o cmd -f to_layout_index * Switch to the layout with the given index in self.
↳layouts.
-o cmd -f to_screen      * Warp focus to screen n, where n is a 0-based screen
↳number
-o cmd -f togroup        * Launch prompt widget to move current window to a given
↳group
-o cmd -f tracemalloc_dump Dump tracemalloc snapshot
-o cmd -f tracemalloc_toggle Toggle tracemalloc status
-o cmd -f warning        Set log level to WARNING
-o cmd -f windows        Return info for each client window

```

1.4.4 qtile run-cmd

Run a command applying rules to the new windows, ie, you can start a window in a specific group, make it floating, intrusive, etc.

The Windows must have NET_WM_PID.

```
# run xterm floating on group "test-group"
qtile run-cmd -g test-group -f xterm
```

1.4.5 qtile top

Is a top like to measure memory usage of Qtile's internals.

1.4.6 dqtile-cmd

A Rofi/dmenu interface to qtile-cmd. Accepts all arguments of qtile-cmd.

Examples:

Output of dqtile-cmd -o cmd

```
dmenu: -
Alt-l  Prompt for args and show function help (if -f is present)
..     Go back to menu.
C-u    Clear input
Esc    Exit
-o cmd -f add_rule      * Add a dgroup rule, returns rule_id needed to remove it
-o cmd -f addgroup     * Add a group with the given name
-o cmd -f commands     Returns a list of possible commands for this object
-o cmd -f critical     Set log level to CRITICAL
-o cmd -f debug        Set log level to DEBUG
-o cmd -f delgroup     * Delete a group with the given name
-o cmd -f display_kb   * Display table of key bindings
-o cmd -f doc          * Returns the documentation for a specified command name
-o cmd -f error        Set log level to ERROR
-o cmd -f eval         * Evaluates code in the same context as this function
-o cmd -f findwindow  * Launch prompt widget to find a window of the given name
-o cmd -f focus_by_click * Bring a window to the front
-o cmd -f function     * Call a function with current object as argument
-o cmd -f get_info     Prints info for all groups
-o cmd -f get_state    Get pickled state for restarting qtile
```

Output of `dqtile-cmd -h`

```
dqtile-cmd

  A Rofi/dmenu interface to qtile-cmd. Excepts all arguments of qtile-cmd
  (see below).

usage: dqtile-cmd [-h] [--object OBJ_SPEC [OBJ_SPEC ...]]
                 [--function FUNCTION] [--args ARGS [ARGS ...]] [--info]

Simple tool to expose qtile.command functionality to shell.

optional arguments:
  -h, --help            show this help message and exit
  --object OBJ_SPEC [OBJ_SPEC ...], -o OBJ_SPEC [OBJ_SPEC ...]
                        Specify path to object (space separated). If no
                        --function flag display available commands.
  --function FUNCTION, -f FUNCTION
                        Select function to execute.
  --args ARGS [ARGS ...], -a ARGS [ARGS ...]
                        Set arguments supplied to function.
  --info, -i           With both --object and --function args prints
                        documentation for function.

Examples:
dqtile-cmd
dqtile-cmd -o cmd
dqtile-cmd -o cmd -f prev_layout -i
dqtile-cmd -o cmd -f prev_layout -a 3 # prev_layout on group 3
dqtile-cmd -o group 3 -f focus_back

If both rofi and dmenu are present rofi will be selected as default, to change this us --
↔force-dmenu as the first argument.
```

1.4.7 iqshell

In addition to the standard `qtile shell` shell interface, we provide a kernel capable of running through Jupyter that hooks into the `qshell` client. The command structure and syntax is the same as `qshell`, so it is recommended you read that for more information about that.

Dependencies

In order to run `iqshell`, you must have `ipykernel` and `jupyter_console`. You can install the dependencies when you are installing `qtile` by running:

```
$ pip install qtile[ipython]
```

Otherwise, you can just install these two packages separately, either through PyPI or through your distribution package manager.

Installing and Running the Kernel

Once you have the required dependencies, you can run the kernel right away by running:

```
$ python3 -m libqtile.interactive.iqshell_kernel
```

However, this will merely spawn a kernel instance, you will have to run a separate frontend that connects to this kernel.

A more convenient way to run the kernel is by registering the kernel with Jupyter. To register the kernel itself, run:

```
$ python3 -m libqtile.interactive.iqshell_install
```

If you run this as a non-root user, or pass the `--user` flag, this will install to the user Jupyter kernel directory. You can now invoke the kernel directly when starting a Jupyter frontend, for example:

```
$ jupyter console --kernel qshell
```

The `iqshell` script will launch a Jupyter terminal console with the `qshell` kernel.

iqshell vs qtile shell

One of the main drawbacks of running through a Jupyter kernel is the frontend has no way to query the current node of the kernel, and as such, there is no way to set a custom prompt. In order to query your current node, you can call `pwd`.

This, however, enables many of the benefits of running in a Jupyter frontend, including being able to save, run, and re-run code cells in frontends such as the Jupyter notebook.

The Jupyter kernel also enables more advanced help, text completion, and introspection capabilities (however, these are currently not implemented at a level much beyond what is available in the standard `qtile` shell).

- *Built-in Extensions*
- *Built-in Hooks*
- *Built-in Layouts*
- *Built-in Widgets*

1.5 Reference

1.5.1 Built-in Hooks

`subscribe.addgroup(func)`

Called when group is added

Arguments

- name of new group

`subscribe.changegroup(func)`

Called whenever a group change occurs

Arguments

None

`subscribe.client_focus(func)`
Called whenever focus changes

Arguments

- Window object of the new focus.

`subscribe.client_killed(func)`
Called after a client has been unmanaged

Arguments

- Window object of the killed window.

`subscribe.client_managed(func)`
Called after Qtile starts managing a new client

Called after a window is assigned to a group, or when a window is made static. This hook is not called for internal windows.

Arguments

- Window object of the managed window

`subscribe.client_mouse_enter(func)`
Called when the mouse enters a client

Arguments

- Window of window entered

`subscribe.client_name_updated(func)`
Called when the client name changes

Arguments

- Window of client with updated name

`subscribe.client_new(func)`
Called before Qtile starts managing a new client

Use this hook to declare windows static, or add them to a group on startup. This hook is not called for internal windows.

Arguments

- Window object

Examples

```
@libqtile.hook.subscribe.client_new
def func(c):
    if c.name == "xterm":
        c.togroup("a")
    elif c.name == "dzen":
        c.cmd_static(0)
```

`subscribe.client_urgent_hint_changed(func)`
Called when the client urgent hint changes

Arguments

- Window of client with hint change

`subscribe.current_screen_change(func)`

Called when the current screen (i.e. the screen with focus) changes

Arguments

None

`subscribe.delgroup(func)`

Called when group is deleted

Arguments

- name of deleted group

`subscribe.enter_chord(func)`

Called when key chord begins

Arguments

- name of chord(mode)

`subscribe.float_change(func)`

Called when a change in float state is made

Arguments

None

`subscribe.focus_change(func)`

Called when focus is changed

Arguments

None

`subscribe.group_window_add(func)`

Called when a new window is added to a group

Arguments

- Group receiving the new window
- Window added to the group

`subscribe.layout_change(func)`

Called on layout change

Arguments

- layout object for new layout
- group object on which layout is changed

`subscribe.leave_chord(func)`

Called when key chord ends

Arguments

None

`subscribe.net_wm_icon_change(func)`

Called on `_NET_WM_ICON` chance

Arguments

- Window of client with changed icon

`subscribe.restart(func)`

Called before qtile is restarted

Arguments

None

`subscribe.screen_change(func)`

Called when the output configuration is changed (e.g. via `randr` in X11).

Arguments

- `xproto.randr.ScreenChangeNotify` event (X11) or `None` (Wayland).

`subscribe.selection_change(func)`

Called on selection change

Arguments

- name of the selection
- dictionary describing selection, containing `owner` and `selection` as keys

`subscribe.selection_notify(func)`

Called on selection notify

Arguments

- name of the selection
- dictionary describing selection, containing `owner` and `selection` as keys

`subscribe.setgroup(func)`

Called when group is changed

Arguments

None

`subscribe.shutdown(func)`

Called before qtile is shutdown

Arguments

None

`subscribe.startup(func)`

Called when qtile is started

Arguments

None

`subscribe.startup_complete(func)`

Called when qtile is started after all resources initialized

Arguments

None

`subscribe.startup_once(func)`

Called when Qtile has started on first start

This hook is called exactly once per session (i.e. not on each `lazy.restart()`).

Arguments

None

1.5.2 Built-in Layouts

Floating

class `libqtile.layout.floating.Floating(float_rules=None, no_reposition_rules=None, **config)`
Floating layout, which does nothing with windows but handles focus order

key	default	description
<code>border_focus</code>	<code>'#0000ff'</code>	'Border colour for the focused window.'
<code>border_normal</code>	<code>'#000000'</code>	'Border colour for un-focused windows.'
<code>border_width</code>	<code>1</code>	'Border width.'
<code>fullscreen_border_width</code>	<code>0</code>	'Border width for fullscreen.'
<code>max_border_width</code>	<code>0</code>	'Border width for maximize.'

Bsp

class `libqtile.layout.bsp.Bsp(**config)`

This layout is inspired by bspwm, but it does not try to copy its features.

The first client occupies the entire screen space. When a new client is created, the selected space is partitioned in 2 and the new client occupies one of those subspaces, leaving the old client with the other.

The partition can be either horizontal or vertical according to the dimensions of the current space: if its width/height ratio is above a pre-configured value, the subspaces are created side-by-side, otherwise, they are created on top of each other. The partition direction can be freely toggled. All subspaces can be resized and clients can be shuffled around.

All clients are organized at the leaves of a full binary tree.

An example key configuration is:

```
Key([mod], "j", lazy.layout.down()),
Key([mod], "k", lazy.layout.up()),
Key([mod], "h", lazy.layout.left()),
Key([mod], "l", lazy.layout.right()),
Key([mod], "shift", "j", lazy.layout.shuffle_down()),
Key([mod], "shift", "k", lazy.layout.shuffle_up()),
Key([mod], "shift", "h", lazy.layout.shuffle_left()),
Key([mod], "shift", "l", lazy.layout.shuffle_right()),
Key([mod], "mod1", "j", lazy.layout.flip_down()),
Key([mod], "mod1", "k", lazy.layout.flip_up()),
Key([mod], "mod1", "h", lazy.layout.flip_left()),
Key([mod], "mod1", "l", lazy.layout.flip_right()),
Key([mod], "control", "j", lazy.layout.grow_down()),
Key([mod], "control", "k", lazy.layout.grow_up()),
Key([mod], "control", "h", lazy.layout.grow_left()),
Key([mod], "control", "l", lazy.layout.grow_right()),
Key([mod], "shift", "n", lazy.layout.normalize()),
Key([mod], "Return", lazy.layout.toggle_split()),
```

key	default	description
border_focus	'#881111'	'Border colour for the focused window.'
border_normal	'#220000'	'Border colour for un-focused windows.'
border_width	2	'Border width.'
fair	True	'New clients are inserted in the shortest branch.'
grow_amount	10	'Amount by which to grow a window/column.'
lower_right	True	'New client occupies lower or right subspace.'
margin	0	'Margin of the layout (int or list of ints [N E S W]).'
ratio	1.6	'Width/height ratio that defines the partition direction.'

Columns

class libqtile.layout.columns.Columns(**config)

Extension of the Stack layout.

The screen is split into columns, which can be dynamically added or removed. Each column can present its windows in 2 modes: split or stacked. In split mode, all windows are presented simultaneously, splitting the column space. In stacked mode, only a single window is presented from the stack of windows. Columns and windows can be resized and windows can be shuffled around.

This layout can also emulate wmi's default layout via:

```
layout.Columns(num_columns=1, insert_position=1)
```

Or the "Vertical", and "Max", depending on the default parameters.

An example key configuration is:

```
Key([mod], "j", lazy.layout.down()),
Key([mod], "k", lazy.layout.up()),
Key([mod], "h", lazy.layout.left()),
Key([mod], "l", lazy.layout.right()),
Key([mod], "shift", "j", lazy.layout.shuffle_down()),
Key([mod], "shift", "k", lazy.layout.shuffle_up()),
Key([mod], "shift", "h", lazy.layout.shuffle_left()),
Key([mod], "shift", "l", lazy.layout.shuffle_right()),
Key([mod], "control", "j", lazy.layout.grow_down()),
Key([mod], "control", "k", lazy.layout.grow_up()),
Key([mod], "control", "h", lazy.layout.grow_left()),
Key([mod], "control", "l", lazy.layout.grow_right()),
Key([mod], "shift", "control", "h", lazy.layout.swap_column_left()),
Key([mod], "shift", "control", "l", lazy.layout.swap_column_right()),
Key([mod], "Return", lazy.layout.toggle_split()),
Key([mod], "n", lazy.layout.normalize()),
```

key	default	description
<code>border_focus</code>	<code>'#881111'</code>	'Border colour for the focused window.'
<code>border_focus_stacked</code>	<code>'#881111'</code>	'Border colour for the focused window in stacked columns.'
<code>border_normal</code>	<code>'#220000'</code>	'Border colour for un-focused windows.'
<code>border_normal_stacked</code>	<code>'#220000'</code>	'Border colour for un-focused windows in stacked columns.'
<code>border_on_single</code>	<code>False</code>	'Draw a border when there is one only window.'
<code>border_width</code>	<code>2</code>	'Border width.'
<code>fair</code>	<code>False</code>	'Add new windows to the column with least windows.'
<code>grow_amount</code>	<code>10</code>	'Amount by which to grow a window/column.'
<code>insert_position</code>	<code>0</code>	'Position relative to the current window where new ones are inserted (0 means right above the current window, 1 means right after).'
<code>margin</code>	<code>0</code>	'Margin of the layout (int or list of ints [N E S W]).'
<code>margin_on_single</code>	<code>None</code>	'Margin when only one window. (int or list of ints [N E S W])'
<code>num_columns</code>	<code>2</code>	'Preferred number of columns.'
<code>split</code>	<code>True</code>	'New columns presentation mode.'
<code>wrap_focus_columns</code>	<code>True</code>	'Wrap the screen when moving focus across columns.'
<code>wrap_focus_rows</code>	<code>True</code>	'Wrap the screen when moving focus across rows.'
<code>wrap_focus_stacks</code>	<code>True</code>	'Wrap the screen when moving focus across stacked.'

Matrix

class `libqtile.layout.matrix.Matrix`(*columns=2, **config*)

This layout divides the screen into a matrix of equally sized cells and places one window in each cell. The number of columns is configurable and can also be changed interactively.

key	default	description
<code>border_focus</code>	<code>'#0000ff'</code>	'Border colour for the focused window.'
<code>border_normal</code>	<code>'#000000'</code>	'Border colour for un-focused windows.'
<code>border_width</code>	<code>1</code>	'Border width.'
<code>margin</code>	<code>0</code>	'Margin of the layout (int or list of ints [N E S W])'

Max

class `libqtile.layout.max.Max`(***config*)

Maximized layout

A simple layout that only displays one window at a time, filling the `screen_rect`. This is suitable for use on laptops and other devices with small screens. Conceptually, the windows are managed as a stack, with commands to switch to next and previous windows in the stack.


MonadTall

class libqtile.layout.xmonad.**MonadTall**(***config*)


Emulate the behavior of XMonad’s default tiling scheme.

Main-Pane:

A main pane that contains a single window takes up a vertical portion of the screen_rect based on the ratio setting. This ratio can be adjusted with the `cmd_grow_main` and `cmd_shrink_main` or, while the main pane is in focus, `cmd_grow` and `cmd_shrink`.




Using the `cmd_flip` method will switch which horizontal side the main pane will occupy. The main pane is considered the “top” of the stack.




Secondary-panes:

Occupying the rest of the screen_rect are one or more secondary panes. The secondary panes will share the vertical space of the screen_rect however they can be resized at will with the `cmd_grow` and `cmd_shrink` methods. The other secondary panes will adjust their sizes to smoothly fill all of the space.




Panes can be moved with the `cmd_shuffle_up` and `cmd_shuffle_down` methods. As mentioned the main pane is considered the top of the stack; moving up is counter-clockwise and moving down is clockwise.

The opposite is true if the layout is “flipped”.



(continues on next page)

(continued from previous page)

**Normalizing/Resetting:**

To restore all secondary client windows to their default size ratios use the `cmd_normalize` method.

To reset all client windows to their default sizes, including the primary window, use the `cmd_reset` method.

Maximizing:

To toggle a client window between its minimum and maximum sizes simply use the `cmd_maximize` on a focused client.

Suggested Bindings:

```
Key([modkey], "h", lazy.layout.left()),
Key([modkey], "l", lazy.layout.right()),
Key([modkey], "j", lazy.layout.down()),
Key([modkey], "k", lazy.layout.up()),
Key([modkey], "shift", "h", lazy.layout.swap_left()),
Key([modkey], "shift", "l", lazy.layout.swap_right()),
Key([modkey], "shift", "j", lazy.layout.shuffle_down()),
Key([modkey], "shift", "k", lazy.layout.shuffle_up()),
Key([modkey], "i", lazy.layout.grow()),
Key([modkey], "m", lazy.layout.shrink()),
Key([modkey], "n", lazy.layout.normalize()),
Key([modkey], "o", lazy.layout.maximize()),
Key([modkey], "shift", "space", lazy.layout.flip()),
```

key	default	description
<code>align</code>	<code>0</code>	'Which side master plane will be placed (one of <code>MonadTall._left</code> or <code>MonadTall._right</code>)'
<code>border_focus</code>	<code>'#ff0000'</code>	'Border colour for the focused window.'
<code>border_normal</code>	<code>'#000000'</code>	'Border colour for un-focused windows.'
<code>border_width</code>	<code>2</code>	'Border width.'
<code>change_ratio</code>	<code>0.05</code>	'Resize ratio'
<code>change_size</code>	<code>20</code>	'Resize change in pixels'
<code>margin</code>	<code>0</code>	'Margin of the layout'
<code>max_ratio</code>	<code>0.75</code>	'The percent of the screen-space the master pane should occupy at maximum.'
<code>min_ratio</code>	<code>0.25</code>	'The percent of the screen-space the master pane should occupy at minimum.'
<code>min_secondary_size</code>	<code>85</code>	'minimum size in pixel for a secondary pane window'
<code>new_client_position</code>	<code>'after_current'</code>	'Place new windows : <code>after_current</code> - after the active window, <code>before_current</code> - before the active window, <code>top</code> - at the top of the stack, <code>bottom</code> - at the bottom of the stack.'
<code>ratio</code>	<code>0.5</code>	'The percent of the screen-space the master pane should occupy by default.'
<code>single_border_width</code>	<code>None</code>	'Border width for single window'
<code>single_margin</code>	<code>None</code>	'Margin size for single window'

MonadWide

`class libqtile.layout.xmonad.MonadWide(**config)`

Emulate the behavior of XMonad’s horizontal tiling scheme.

This layout attempts to emulate the behavior of XMonad wide tiling scheme.

Main-Pane:

A main pane that contains a single window takes up a horizontal portion of the screen_rect based on the ratio setting. This ratio can be adjusted with the `cmd_grow_main` and `cmd_shrink_main` or, while the main pane is in focus, `cmd_grow` and `cmd_shrink`.




Using the `cmd_flip` method will switch which vertical side the main pane will occupy. The main pane is considered the “top” of the stack.




Secondary-panes:

Occupying the rest of the screen_rect are one or more secondary panes. The secondary panes will share the horizontal space of the screen_rect however they can be resized at will with the `cmd_grow` and `cmd_shrink` methods. The other secondary panes will adjust their sizes to smoothly fill all of the space.




Panes can be moved with the `cmd_shuffle_up` and `cmd_shuffle_down` methods. As mentioned the main pane is considered the top of the stack; moving up is counter-clockwise and moving down is clockwise.

The opposite is true if the layout is “flipped”.



(continues on next page)

(continued from previous page)

**Normalizing/Resetting:**

To restore all secondary client windows to their default size ratios use the `cmd_normalize` method.

To reset all client windows to their default sizes, including the primary window, use the `cmd_reset` method.

Maximizing:

To toggle a client window between its minimum and maximum sizes simply use the `cmd_maximize` on a focused client.

Suggested Bindings:

```
Key([modkey], "h", lazy.layout.left()),
Key([modkey], "l", lazy.layout.right()),
Key([modkey], "j", lazy.layout.down()),
Key([modkey], "k", lazy.layout.up()),
Key([modkey], "shift", "h", lazy.layout.swap_left()),
Key([modkey], "shift", "l", lazy.layout.swap_right()),
Key([modkey], "shift", "j", lazy.layout.shuffle_down()),
Key([modkey], "shift", "k", lazy.layout.shuffle_up()),
Key([modkey], "i", lazy.layout.grow()),
Key([modkey], "m", lazy.layout.shrink()),
Key([modkey], "n", lazy.layout.normalize()),
Key([modkey], "o", lazy.layout.maximize()),
Key([modkey], "shift", "space", lazy.layout.flip()),
```

key	default	description
align	0	'Which side master plane will be placed (one of MonadTall._left or MonadTall._right)'
border_focus	'#ff0000'	'Border colour for the focused window.'
border_normal	'#000000'	'Border colour for un-focused windows.'
border_width	2	'Border width.'
change_ratio	0.05	'Resize ratio'
change_size	20	'Resize change in pixels'
margin	0	'Margin of the layout'
max_ratio	0.75	'The percent of the screen-space the master pane should occupy at maximum.'
min_ratio	0.25	'The percent of the screen-space the master pane should occupy at minimum.'
min_secondary_size	85	'minimum size in pixel for a secondary pane window '
new_client_position	after_current	'Place new windows : after_current - after the active window, before_current - before the active window, top - at the top of the stack, bottom - at the bottom of the stack,'
ratio	0.5	'The percent of the screen-space the master pane should occupy by default.'
single_border_width	None	'Border width for single window'
single_margin	None	'Margin size for single window'

RatioTile

class libqtile.layout.ratiotile.**RatioTile**(***config*)

Tries to tile all windows in the width/height ratio passed in

key	default	description
border_focus	'#0000ff'	'Border colour for the focused window.'
border_normal	'#000000'	'Border colour for un-focused windows.'
border_width	1	'Border width.'
fancy	False	'Use a different method to calculate window sizes.'
margin	0	'Margin of the layout (int or list of ints [N E S W])'
ratio	1.618	'Ratio of the tiles'
ratio_increment	0.1	'Amount to increment per ratio increment'

Slice

class `libqtile.layout.slice.Slice(**config)`

Slice layout

This layout cuts piece of `screen_rect` and places a single window on that piece, and delegates other window placement to other layout

key	default	description
<code>fallback</code>	<code><libqtile.layout.max.Max object at 0x7f47afdda290></code>	'Layout to be used for the non-slice area.'
<code>match</code>	<code>None</code>	'Match-object describing which window(s) to move to the slice.'
<code>side</code>	<code>'left'</code>	'Position of the slice (left, right, top, bottom).'
<code>width</code>	<code>256</code>	'Slice width.'

Stack

class `libqtile.layout.stack.Stack(**config)`

A layout composed of stacks of windows

The stack layout divides the `screen_rect` horizontally into a set of stacks. Commands allow you to switch between stacks, to next and previous windows within a stack, and to split a stack to show all windows in the stack, or unsplit it to show only the current window.

Unlike the columns layout the number of stacks is fixed.

key	default	description
<code>autosplit</code>	<code>False</code>	'Auto split all new stacks.'
<code>border_focus</code>	<code>'#0000ff'</code>	'Border colour for the focused window.'
<code>border_normal</code>	<code>'#000000'</code>	'Border colour for un-focused windows.'
<code>border_width</code>	<code>1</code>	'Border width.'
<code>fair</code>	<code>False</code>	'Add new windows to the stacks in a round robin way.'
<code>margin</code>	<code>0</code>	'Margin of the layout (int or list of ints [N E S W])'
<code>num_stacks</code>	<code>2</code>	'Number of stacks.'

Tile

class `libqtile.layout.tile.Tile(**config)`

A layout with two stacks of windows dividing the screen

The Tile layout divides the `screen_rect` horizontally into two stacks. The maximum amount of “master” windows can be configured; surplus windows will be displayed in the slave stack on the right. Within their stacks, the windows will be tiled vertically. The windows can be rotated in their entirety by calling `up()` or `down()` or, if `shift_windows` is set to `True`, individually.

key	default	description
add_after_last	False	'Add new clients after all the others. If this is True, it overrides add_on_top.'
add_on_top	True	'Add new clients before all the others, potentially pushing other windows into slave stack.'
border_focus	'#0000ff'	'Border colour for the focused window.'
border_normal	'#000000'	'Border colour for un-focused windows.'
border_width	1	'Border width.'
expand	True	'Expand the master windows to the full screen width if no slaves are present.'
margin	0	'Margin of the layout (int or list of ints [N E S W])'
master_length	1	'Amount of windows displayed in the master stack. Surplus windows will be moved to the slave stack.'
master_match	None	'A Match object defining which window(s) should be kept masters.'
ratio	0.618	'Width-percentage of screen size reserved for master windows.'
ratio_increment	0.05	'By which amount to change ratio when cmd_decrease_ratio or cmd_increase_ratio are called.'
shift_windows	False	'Allow to shift windows within the layout. If False, the layout will be rotated instead.'

TreeTab

class libqtile.layout.tree.**TreeTab**(**config)

Tree Tab Layout

This layout works just like Max but displays tree of the windows at the left border of the screen_rect, which allows you to overview all opened windows. It's designed to work with uzbl-browser but works with other windows too.

The panel at the left border contains sections, each of which contains windows. Initially the panel looks like flat lists inside its section, and looks like trees if some of the windows are "moved" left or right.

For example, it looks like below with two sections initially:

```
+-----+
|Section Foo |
+-----+
| Window A   |
+-----+
| Window B   |
+-----+
| Window C   |
+-----+
|Section Bar |
+-----+
```

And then it will look like below if "Window B" is moved right and "Window C" is moved right too:

```
+-----+
|Section Foo |
+-----+
| Window A   |
```

(continues on next page)

(continued from previous page)

```
+-----+
| Window B |
+-----+
| Window C |
+-----+
|Section Bar |
+-----+
```

key	default	description
active_bg	'000080'	'Background color of active tab'
active_fg	'ffffff'	'Foreground color of active tab'
bg_color	'000000'	'Background color of tabs'
border_width	2	'Width of the border'
font	'sans'	'Font'
fontshadow	None	'font shadow color, default is None (no shadow)'
fontsize	14	'Font pixel size.'
inactive_bg	'606060'	'Background color of inactive tab'
inactive_fg	'ffffff'	'Foreground color of inactive tab'
level_shift	8	'Shift for children tabs'
margin_left	6	'Left margin of tab panel'
margin_y	6	'Vertical margin of tab panel'
padding_left	6	'Left padding for tabs'
padding_x	6	'Left padding for tab label'
padding_y	2	'Top padding for tab label'
panel_width	150	'Width of the left panel'
previous_on_rm	False	'Focus previous window on close instead of first.'
section_bottom	6	'Bottom margin of section'
section_fg	'ffffff'	'Color of section label'
section_fontsize	11	'Font pixel size of section label'
section_left	4	'Left margin of section label'
section_padding	4	'Bottom of margin section label'
section_top	4	'Top margin of section label'
sections	['Default']	'Foreground color of inactive tab'
urgent_bg	'ff0000'	'Background color of urgent tab'
urgent_fg	'ffffff'	'Foreground color of urgent tab'
vspace	2	'Space between tabs'

VerticalTile

class libqtile.layout.verticaltile.**VerticalTile**(***config*)


Tiling layout that works nice on vertically mounted monitors

The available height gets divided by the number of panes, if no pane is maximized. If one pane has been maximized, the available height gets split in master- and secondary area. The maximized pane (master pane) gets the full height of the master area and the other panes (secondary panes) share the remaining space. The master area (at default 75%) can grow and shrink via keybindings.


```
-----
|           |           |           |           |
|           | <-- Panes |           |           |
|           |           |           |           |
```

(continues on next page)

(continued from previous page)



Normal behavior. No One maximized pane in the master area maximized pane. No and two secondary panes in the specific areas. secondary area.



Suggested keybindings:

```
Key([modkey], 'j', lazy.layout.down()),
Key([modkey], 'k', lazy.layout.up()),
Key([modkey], 'Tab', lazy.layout.next()),
Key([modkey], 'shift', 'Tab', lazy.layout.next()),
Key([modkey], 'shift', 'j', lazy.layout.shuffle_down()),
Key([modkey], 'shift', 'k', lazy.layout.shuffle_up()),
Key([modkey], 'm', lazy.layout.maximize()),
Key([modkey], 'n', lazy.layout.normalize()),
```

key	default	description
border_focus	'#FF0000'	'Border color for the focused window.'
border_normal	'#FFFFFF'	'Border color for un-focused windows.'
border_width	1	'Border width.'
margin	0	'Border margin (int or list of ints [N E S W]).'

Zoomy

class libqtile.layout.zoomy.**Zoomy**(**config)

A layout with single active windows, and few other previews at the right

key	default	description
columnwidth	150	‘Width of the right column’
margin	0	‘Margin of the layout (int or list of ints [N E S W])’
property_big	'1.0'	‘Property value to set on normal window’
property_name	'ZOOM'	‘Property to set on zoomed window’
property_small	'0.1'	‘Property value to set on zoomed window’

1.5.3 Built-in Widgets

AGroupBox

class libqtile.widget.**AGroupBox**(**config)

A widget that graphically displays the current group

Supported bar orientations: horizontal only

key	default	description
background	None	‘Widget background color’
border	'000000'	‘group box border color’
borderwidth	3	‘Current group border width’
center_aligned	True	‘center-aligned group box’
fmt	'{'}	‘How to format the text’
font	'sans'	‘Default font’
fontshadow	None	‘font shadow color, default is None(no shadow)’
fontsize	None	‘Font size. Calculated if None.’
foreground	'ffffff'	‘Foreground colour’
margin	3	‘Margin inside the box’
margin_x	None	‘X Margin. Overrides ‘margin’ if set’
margin_y	None	‘Y Margin. Overrides ‘margin’ if set’
markup	True	‘Whether or not to use pango markup’
max_chars	0	‘Maximum number of characters to display in widget.’
mouse_callbacks	{}	‘Dict of mouse button press callback functions.’
padding	None	‘Padding. Calculated if None.’
padding_x	None	‘X Padding. Overrides ‘padding’ if set’
padding_y	None	‘Y Padding. Overrides ‘padding’ if set’

Backlight

class libqtile.widget.**Backlight**(**config)

A simple widget to show the current brightness of a monitor.

If the `change_command` parameter is set to `None`, the widget will attempt to use the interface at `/sys/class` to change brightness. Depending on the setup, the user may need to be added to the video group to have permission to write to this interface. This depends on having the correct udev rules the brightness file; these are typically installed alongside brightness tools such as `brightnessctl` (which changes the group to ‘video’) so installing that is an easy way to get it working.

You can also bind keyboard shortcuts to the backlight widget with:

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
backlight_name	'acpi_video0'	'ACPI name of a backlight device'
brightness_file	'brightness'	'Name of file with the current brightness in /sys/class/backlight/backlight_name'
change_command	'xbacklight -set {0}'	'Execute command to change value'
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'{percent:2. 0%}'	'Display format'
markup	True	'Whether or not to use pango markup'
max_brightness_file	max_brightness'	'Name of file with the maximum brightness in /sys/class/backlight/backlight_name'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
step	10	'Percent of backlight every scroll changed'
update_interval	0.2	'The delay in seconds between updates'

Battery

class libqtile.widget.**Battery**(***config*)

A text-based battery monitoring widget currently supporting FreeBSD

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
battery	0	'Which battery should be monitored (battery number or name)'
charge_char	'^'	'Character to indicate the battery is charging'
discharge_char	'V'	'Character to indicate the battery is discharging'
empty_char	'x'	'Character to indicate the battery is empty'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'{char} {percent:2.0%} {hour:d}:{min:02d} {watt:.2f} W'	'Display format'
full_char	'='	'Character to indicate the battery is full'
hide_threshold	None	'Hide the text when there is enough energy $0 \leq x < 1$ '
low_foreground	'FF0000'	'Font color on low battery'
low_percentage	0.1	'Indicates when to use the low_foreground color $0 < x < 1$ '
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
notify_below	None	'Send a notification below this battery level.'
padding	None	'Padding. Calculated if None.'
show_short_text	True	'Show "Full" or "Empty" rather than formatted text'
unknown_char	'?'	'Character to indicate the battery status is unknown'
update_interval	60	'Seconds between status updates'

BatteryIcon

class libqtile.widget.**BatteryIcon**(***config*)

Battery life indicator widget.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
battery	0	'Which battery should be monitored'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
theme_path	'/home/docs/ checkouts/ readthedocs. org/ user_builds/ qtile/ checkouts/v0. 18.0/libqtile/ resources/ battery-icons'	'Path of the icons'
update_interval	60	'Seconds between status updates'

BitcoinTicker

class libqtile.widget.**BitcoinTicker**(**config)

A bitcoin ticker widget, data provided by the coinbase.com API. Defaults to displaying currency in whatever the current locale is. Examples:

```
# display the average price of bitcoin in local currency
widget.BitcoinTicker()

# display it in Euros:
widget.BitcoinTicker(currency="EUR")
```

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
currency	' '	'The currency the value that bitcoin is displayed in'
data	None	'Post Data'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
headers	{}	'Extra Headers'
json	True	'Is Json?'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
parse	None	'Parse Function'
update_interval	600	'Update interval in seconds, if none, the widget updates whenever it's done.'
url	None	'Url'
user_agent	'Qtile'	'Set the user agent'
xml	False	'Is XML?'

Bluetooth

class libqtile.widget.**Bluetooth**(**config)

Displays bluetooth status or connected device.

Uses dbus to communicate with the system bus.

Widget requirements: [dbus-next](#).

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
hci	' / dev_XX_XX_XX_XX.XX.XX '	'hci0 device path, can be found with d-feet or similar dbus ex- plorer'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'

CPU

class libqtile.widget.CPU(**config)

A simple widget to display CPU load and frequency.

Widget requirements: [psutil](#).

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
format	' CPU {freq_current}GHz {load_percent}%'	'CPU display format'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
update_interval	1.0	'Update interval for the CPU widget'

CPUGraph

class libqtile.widget.CPUGraph(**config)

Display CPU usage graph.

Widget requirements: [psutil](#).

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
border_color	'215578'	'Widget border color'
border_width	2	'Widget border width'
core	'all'	'Which core to show (all/0/1/2/...)'
fill_color	'1667EB.3'	'Fill color for linefill graph'
frequency	1	'Update frequency in seconds'
graph_color	'18BAEB'	'Graph color'
line_width	3	'Line width'
margin_x	3	'Margin X'
margin_y	3	'Margin Y'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
samples	100	'Count of graph samples.'
start_pos	'bottom'	'Drawer starting position ('bottom'/'top')'
type	'linefill'	'"box", "line", "linefill"'

Canto

class libqtile.widget.**Canto**(***config*)

Display RSS feeds updates using the canto console reader

Supported bar orientations: horizontal only

key	default	description
all_format	'{number}'	'All feeds display format'
background	None	'Widget background color'
feeds	[]	'List of feeds to display, empty for all'
fetch	False	'Whether to fetch new items on update'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
one_format	'{name}:' '{number}'	'One feed display format'
padding	None	'Padding. Calculated if None.'
update_interval	600	'Update interval in seconds, if none, the widget updates whenever it's done.'

CapsNumLockIndicator

class libqtile.widget.**CapsNumLockIndicator**(***config*)

Really simple widget to show the current Caps/Num Lock state.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
update_interval	0.5	'Update Time in seconds.'

CheckUpdates

class libqtile.widget.**CheckUpdates**(***config*)

Shows number of pending updates in different unix systems

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
colour_have_updates	' fffffff '	'Colour when there are updates.'
colour_no_updates	' fffffff '	'Colour when there's no updates.'
custom_command	None	'Custom shell command for checking updates (counts the lines of the output)'
custom_command_modifier	function CheckUpdates. <lambda> at 0x7f47af975a70>	'Lambda function to modify line count from custom_command'
display_format	'Updates: {updates}'	'Display format if updates available'
distro	' Arch '	'Name of your distribution'
execute	None	'Command to execute on click'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
no_update_string	' '	'String to display if no updates available'
padding	None	'Padding. Calculated if None.'
restart_indicator	' '	'Indicator to represent reboot is required. (Ubuntu only)'
update_interval	60	'Update interval in seconds.'

Chord

class libqtile.widget.**Chord**(width=CALCULATED, **config)

Display current key chord

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
chords_colors	{}	"colors per chord in form of tuple ('bg', 'fg')."
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
name_transform	<function Chord. <lambda> at 0x7f47af9930e0>	'preprocessor for chord name it is pure function string -> string'
padding	None	'Padding. Calculated if None.'

Clipboard

class libqtile.widget.**Clipboard**(width=CALCULATED, **config)

Display current clipboard contents

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
blacklist	['keepassx']	'list with blacklisted wm_class, sadly not every clipboard window sets them, keepassx does.Clipboard contents from blacklisted wm_classes will be replaced by the value of blacklist_text.'
blacklist_text	'*****'	'text to display when the wm_class is blacklisted'
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
max_width	10	'maximum number of characters to display (None for all, useful when width is bar.STRETCH)'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
selection	'CLIPBOARD'	'the selection to display(CLIPBOARD or PRIMARY)'
timeout	10	'Default timeout (seconds) for display text, None to keep forever'

Clock

class libqtile.widget.**Clock**(**config)

A simple but flexible text-based clock

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' ffffff '	'Foreground colour'
format	'%H:%M'	'A Python datetime format string'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
timezone	None	'The timezone to use for this clock, either as string if pytz or dateutil is installed (e.g. "US/Central" or anything in /usr/share/zoneinfo), or as tzinfo (e.g. datetime.timezone.utc). None means the system local timezone and is the default.'
update_interval	1.0	'Update interval for the clock'

Cmus

class libqtile.widget.**Cmus**(**config)

A simple Cmus widget.

Show the artist and album of now listening song and allow basic mouse control from the bar:

- toggle pause (or play if stopped) on left click;
- skip forward in playlist on scroll up;
- skip backward in playlist on scroll down.

Cmus (<https://cmus.github.io>) should be installed.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
noplay_color	'cecece'	'Text colour when not playing.'
padding	None	'Padding. Calculated if None.'
play_color	'00ff00'	'Text colour when playing.'
update_interval	0.5	'Update Time in seconds.'

Countdown

class libqtile.widget.Countdown(**config)

A simple countdown timer text widget

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
date	datetime.datetime(2021, 7, 4, 16, 1, 18, 551479)	'The datetime for the endo of the countdown'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'{D}d {H}h {M}m {S}s'	'Format of the displayed text. Available variables: {D} == days, {H} == hours, {M} == minutes, {S} seconds.'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
update_interval	1.0	'Update interval in seconds for the clock'

CurrentLayout

class libqtile.widget.**CurrentLayout**(width=CALCULATED, **config)

Display the name of the current layout of the current group of the screen, the bar containing the widget, is on.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'

CurrentLayoutIcon

class libqtile.widget.**CurrentLayoutIcon**(**config)

Display the icon representing the current layout of the current group of the screen on which the bar containing the widget is.

If you are using custom layouts, a default icon with question mark will be displayed for them. If you want to use custom icon for your own layout, for example, *FooGrid*, then create a file named "layout-foogrid.png" and place it in *~/.icons* directory. You can as well use other directories, but then you need to specify those directories in *custom_icon_paths* argument for this plugin.

The order of icon search is:

- dirs in *custom_icon_paths* config argument
- *~/.icons*
- built-in qtile icons

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
custom_icon_paths[]		'List of folders where to search icons before using built-in icons or icons in <i>~/.icons</i> dir. This can also be used to provide missing icons for custom layouts. Defaults to empty list.'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
scale	1	'Scale factor relative to the bar height. Defaults to 1'

CurrentScreen

class libqtile.widget.**CurrentScreen**(width=CALCULATED, **config)

Indicates whether the screen this widget is on is currently active or not

Supported bar orientations: horizontal only

key	default	description
active_color	'00ff00'	'Color when screen is active'
active_text	'A'	'Text displayed when the screen is active'
background	None	'Widget background color'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
inactive_color	'ff0000'	'Color when screen is inactive'
inactive_text	'I'	'Text displayed when the screen is inactive'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'

DF

class libqtile.widget.**DF**(**config)

Disk Free Widget

By default the widget only displays if the space is less than warn_space.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'{p} ({uf}{m} {r:. 0f}%)'	'String format (p: partition, s: size, f: free space, uf: user free space, m: measure, r: ratio (uf/s))'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
measure	'G'	'Measurement (G, M, B)'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
partition	'/'	'the partition to check space'
update_interval	60	'The update interval.'
visible_on_warn	True	'Only display if warning'
warn_color	'ff0000'	'Warning color'
warn_space	2	'Warning space in scale defined by the measure option.'

GenPollText

class libqtile.widget.**GenPollText**(***config*)

A generic text widget that polls using poll function to get the text

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
func	None	'Poll Function'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
update_interval	600	'Update interval in seconds, if none, the widget updates whenever it's done.'

GenPollUrl

class libqtile.widget.**GenPollUrl**(***config*)

A generic text widget that polls an url and parses it using parse function

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
data	None	'Post Data'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
headers	{}	'Extra Headers'
json	True	'Is Json?'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
parse	None	'Parse Function'
update_interval	600	'Update interval in seconds, if none, the widget updates whenever it's done.'
url	None	'Url'
user_agent	'Qtile'	'Set the user agent'
xml	False	'Is XML?'

GmailChecker

class libqtile.widget.**GmailChecker**(**config)

A simple gmail checker. If 'status_only_unseen' is True - set 'fmt' for one argument, ex. 'unseen: {0}'

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
display_fmt	'inbox[{}], unseen[{}]'	'Display format'
email_path	'INBOX'	'email_path'
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
password	None	'password'
status_only_unseen	False	'Only show unseen messages'
update_interval	30	'Update time in seconds.'
username	None	'username'

GroupBox

class libqtile.widget.**GroupBox**(**config)

A widget that graphically displays the current group. All groups are displayed by their label. If the label of a group is the empty string that group will not be displayed.

Supported bar orientations: horizontal only

key	default	description
active	'FFFFFF'	'Active group font colour'
background	None	'Widget background color'
block_highlight_text_color	None	'Selected group font colour'
borderwidth	3	'Current group border width'
center_aligned	True	'center-aligned group box'
disable_drag	False	'Disable dragging and dropping of group names on widget'
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
hide_unused	False	'Hide groups that have no windows and that are not displayed on any screen.'
highlight_color	['000000', '282828']	'Active group highlight color when using 'line' highlight method.'

continues on next page

Table 1 – continued from previous page

key	default	description
highlight_method	'border'	“Method of highlighting (‘border’, ‘block’, ‘text’, or ‘line’)Uses * <i>_border</i> color settings”
inactive	'404040'	‘Inactive group font colour’
invert_mouse_wheel	False	‘Whether to invert mouse wheel group movement’
margin	3	‘Margin inside the box’
margin_x	None	“X Margin. Overrides ‘margin’ if set”
margin_y	None	“Y Margin. Overrides ‘margin’ if set”
markup	True	‘Whether or not to use pango markup’
max_chars	0	‘Maximum number of characters to display in widget.’
mouse_callbacks	{}	‘Dict of mouse button press callback functions.’
other_current_screen_border	'404040'	‘Border or line colour for group on other screen when focused.’
other_screen_border	'404040'	‘Border or line colour for group on other screen when unfocused.’
padding	None	‘Padding. Calculated if None.’
padding_x	None	“X Padding. Overrides ‘padding’ if set”
padding_y	None	“Y Padding. Overrides ‘padding’ if set”
rounded	True	‘To round or not to round box borders’
spacing	None	‘Spacing between groups(if set to None, will be equal to margin_x)’
this_current_screen_border	'215578'	‘Border or line colour for group on this screen when focused.’
this_screen_border	'215578'	‘Border or line colour for group on this screen when unfocused.’
urgent_alert_method	'border'	“Method for alerting you of WM urgent hints (one of ‘border’, ‘text’, ‘block’, or ‘line’)”
urgent_border	'FF0000'	‘Urgent border or line color’
urgent_text	'FF0000'	‘Urgent group font color’
use_mouse_wheel	True	‘Whether to use mouse wheel events’
visible_groups	None	‘Groups that will be visible. If set to None or [], all groups will be visible. Visible groups are identified by name not by their displayed label.’

HDDBusyGraph

```
class libqtile.widget.HDDBusyGraph(**config)
```

Display HDD busy time graph

Parses `/sys/block/<dev>/stat` file and extracts overall device IO usage, based on `io_ticks`’s value. See <https://www.kernel.org/doc/Documentation/block/stat.txt>

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
border_color	'215578'	'Widget border color'
border_width	2	'Widget border width'
device	'sda'	'Block device to display info for'
fill_color	'1667EB.3'	'Fill color for linefill graph'
frequency	1	'Update frequency in seconds'
graph_color	'18BAEB'	'Graph color'
line_width	3	'Line width'
margin_x	3	'Margin X'
margin_y	3	'Margin Y'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
samples	100	'Count of graph samples.'
start_pos	'bottom'	'Drawer starting position ('bottom'/'top)'
type	'linefill'	'"box', 'line', 'linefill"'

HDDGraph

class libqtile.widget.HDDGraph(**config)

Display HDD free or used space graph

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
border_color	'215578'	'Widget border color'
border_width	2	'Widget border width'
fill_color	'1667EB.3'	'Fill color for linefill graph'
frequency	1	'Update frequency in seconds'
graph_color	'18BAEB'	'Graph color'
line_width	3	'Line width'
margin_x	3	'Margin X'
margin_y	3	'Margin Y'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
path	'/'	'Partition mount point.'
samples	100	'Count of graph samples.'
space_type	'used'	'free/used'
start_pos	'bottom'	'Drawer starting position ('bottom'/'top)'
type	'linefill'	'"box', 'line', 'linefill"'

IdleRPG

class libqtile.widget.IdleRPG(**config)

A widget for monitoring and displaying IdleRPG stats.

```
# display idlerpg stats for the player 'pants' on freenode's #idlerpg
widget.IdleRPG(url="http://xethron.lolhosting.net/xml.php?player=pants")
```

Widget requirements: `xmltodict`.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
data	None	'Post Data'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'IdleRPG: {online} TTL: {ttl}'	'Display format'
headers	{}	'Extra Headers'
json	False	'Not json :)'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
parse	None	'Parse Function'
update_interval	600	'Update interval in seconds, if none, the widget updates whenever it's done.'
url	None	'Url'
user_agent	'Qtile'	'Set the user agent'
xml	True	'Is XML :)'

Image

class libqtile.widget.**Image**(*length=CALCULATED, width=None, **config*)

Display a PNG image on the bar

Supported bar orientations: horizontal and vertical

key	default	description
background	None	'Widget background color'
filename	None	'Image filename. Can contain '~'
margin	3	'Margin inside the box'
margin_x	None	'X Margin. Overrides 'margin' if set'
margin_y	None	'Y Margin. Overrides 'margin' if set'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
rotate	0.0	'rotate the image in degrees counter-clockwise'
scale	True	'Enable/Disable image scaling'

ImapWidget

class libqtile.widget.ImapWidget(**config)

Email IMAP widget

This widget will scan one of your imap email boxes and report the number of unseen messages present. I've configured it to only work with imap with ssl. Your password is obtained from the Gnome Keyring.

Writing your password to the keyring initially is as simple as (changing out <userid> and <password> for your userid and password):

- 1) create the file `~/.local/share/python_keyring/keyringrc.cfg` with the following contents:

```
[backend]
default-keyring=keyring.backends.Gnome.Keyring
keyring-path=/home/<userid>/.local/share/keyring/
```

- 2) Execute the following python shell script once:

```
#!/usr/bin/env python3
import keyring
user = <userid>
password = <password>
keyring.set_password('imapwidget', user, password)
```

mbox names must include the path to the mbox (except for the default INBOX). So, for example if your mailroot is `~/Maildir`, and you want to look at the mailbox at `HomeMail/fred`, the mbox setting would be: `mbox="~/Maildir/HomeMail/fred"`. Note the nested sets of quotes! Labels can be whatever you choose, of course.

Widget requirements: [keyring](#).

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	'{}'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
label	'INBOX'	'label for display'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mbox	'"INBOX"'	'mailbox to fetch'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
server	None	'email server name'
update_interval	600	'Update interval in seconds, if none, the widget updates whenever it's done.'
user	None	'email username'

KeyboardKbdd

class libqtile.widget.**KeyboardKbdd**(***config*)

Widget for changing keyboard layouts per window, using kbdd

kbdd should be installed and running, you can get it from: <https://github.com/qnikst/kbdd>

The widget also requires `dbus-next`.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
colours	None	'foreground colour for each layout either 'None' or a list of colours.example: ['ffffff', 'E6F0AF']. "
configured_keyboards	['us', 'ir']	'your predefined list of keyboard layouts.example: ['us', 'ir', 'es']"
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
update_interval	1	'Update interval in seconds.'

KeyboardLayout

class libqtile.widget.**KeyboardLayout**(***config*)

Widget for changing and displaying the current keyboard layout

To use this widget effectively you need to specify keyboard layouts you want to use (using "configured_keyboards") and bind function "next_keyboard" to specific keys in order to change layouts.

For example:

```
Key([mod], "space", lazy.widget["keyboardlayout"].next_keyboard(), desc="Next keyboard layout."),
```

When running Qtile with the X11 backend, this widget requires `setxkbmap` to be available.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
configured_keyboards	['us']	"A list of predefined keyboard layouts represented as strings. For example: ['us', 'us colemak', 'es', 'fr']."
display_map	{}	"Custom display of layout. Key should be in format 'layout variant'. For example: {'us': 'us ', 'lt sgs': 'sgs', 'ru phonetic': 'ru '}"
fmt	'{}'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
option	None	"string of setxkbmap option. Ex., 'compose:menu.grp_led:scroll'"
padding	None	'Padding. Calculated if None.'
update_interval	1	'Update time in seconds.'

KhalCalendar

`class libqtile.widget.KhalCalendar(**config)`

Khal calendar widget

This widget will display the next appointment on your Khal calendar in the qtile status bar. Appointments within the "reminder" time will be highlighted.

Widget requirements: [dateutil](#).

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	'{}'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'FFFF33'	'default foreground color'
lookahead	7	'days to look ahead in the calendar'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
reminder_color	'FF0000'	'color of calendar entries during reminder time'
remindertime	10	'reminder time in minutes'
update_interval	600	"Update interval in seconds, if none, the widget updates whenever it's done."

LaunchBar

class libqtile.widget.**LaunchBar**(*progs=None, width=CALCULATED, **config*)

A widget that display icons to launch the associated command

Widget requirements: `pyxdg`.

Parameters

progs: a list of tuples (`software_name`, `command_to_execute`, `comment`), for example:

```
( 'thunderbird', 'thunderbird -safe-mode', 'launch thunderbird in
↳ safe mode')
('logout', 'qshell:self.qtile.cmd_shutdown()', 'logout from qtile')
```

Supported bar orientations: horizontal only

key	default	description
<code>background</code>	<code>None</code>	'Widget background color'
<code>default_icon</code>	<code> '/usr/share/ icons/oxygen/ 256x256/ mimetypes/ application-x-executable. png'</code>	'Default icon not found'
<code>mouse_callbacks</code>	<code>{}</code>	'Dict of mouse button press callback functions.'
<code>padding</code>	<code>2</code>	'Padding between icons'

Maildir

class libqtile.widget.**Maildir**(***config*)

A simple widget showing the number of new mails in maildir mailboxes

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
empty_color	None	'Display color when no new mail is available'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
hide_when_empty	False	'Whether not to display anything if the subfolder has no new mail'
maildir_path	'~/Mail'	'path to the Maildir folder'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
nonempty_color	None	'Display color when new mail is available'
padding	None	'Padding. Calculated if None.'
separator	' '	'the string to put between the subfolder strings.'
sub_folders	[{'label': 'Home mail', 'path': 'INBOX'}, {'label': 'Home junk', 'path': 'spam'}]	'List of subfolders to scan. Each subfolder is a dict of <i>path</i> and <i>label</i> .'
subfolder_fmt	'{label}: {value}'	'Display format for one subfolder'
total	False	'Whether or not to sum subfolders into a grand total. The first label will be used.'
update_interval	600	'Update interval in seconds, if none, the widget updates whenever it's done.'

Memory

class libqtile.widget.**Memory**(***config*)

Displays memory/swap usage

MemUsed: Returns memory in use MemTotal: Returns total amount of memory MemFree: Returns amount of memory free MemPercent: Returns memory in use as a percentage Buffers: Returns buffer amount Active: Returns active memory Inactive: Returns inactive memory Shmem: Returns shared memory SwapTotal: Returns total amount of swap SwapFree: Returns amount of swap free SwapUsed: Returns amount of swap in use SwapPercent: Returns swap in use as a percentage

Widget requirements: [psutil](#).

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'{MemUsed: .0f}{mm}/ {MemTotal: .0f}{mm}'	'Formatting for field names.'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
measure_mem	'M'	'Measurement for Memory (G, M, K, B)'
measure_swap	'M'	'Measurement for Swap (G, M, K, B)'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
update_interval	1.0	'Update interval for the Memory'

MemoryGraph

class libqtile.widget.**MemoryGraph**(***config*)

Displays a memory usage graph.

Widget requirements: `psutil`.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
border_color	'215578'	'Widget border color'
border_width	2	'Widget border width'
fill_color	'1667EB.3'	'Fill color for linefill graph'
frequency	1	'Update frequency in seconds'
graph_color	'18BAEB'	'Graph color'
line_width	3	'Line width'
margin_x	3	'Margin X'
margin_y	3	'Margin Y'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
samples	100	'Count of graph samples.'
start_pos	'bottom'	'Drawer starting position ('bottom'/'top)'
type	'linefill'	'"box', 'line', 'linefill"'

Mirror

class libqtile.widget.**Mirror**(*reflection*, ***config*)

A widget for showing the same widget content in more than one place, for instance, on bars across multiple screens.

You don't need to use it directly; instead, just instantiate your widget once and hand it in to multiple bars. For instance:

```
cpu = widget.CPUGraph()
clock = widget.Clock()

screens = [
    Screen(top=bar.Bar([widget.GroupBox(), cpu, clock])),
    Screen(top=bar.Bar([widget.GroupBox(), cpu, clock])),
]
```

Widgets can be passed to more than one bar, so that there don't need to be any duplicates executing the same code all the time, and they'll always be visually identical.

This works for all widgets that use *drawers* (and nothing else) to display their contents. Currently, this is all widgets except for *Systray*.

Supported bar orientations: horizontal and vertical

key	default	description
background	None	'Widget background color'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'

Moc

class libqtile.widget.**Moc**(***config*)

A simple MOC widget.

Show the artist and album of now listening song and allow basic mouse control from the bar:

- toggle pause (or play if stopped) on left click;
- skip forward in playlist on scroll up;
- skip backward in playlist on scroll down.

MOC (<http://moc.daper.net>) should be installed.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
noplay_color	'cecece'	'Text colour when not playing.'
padding	None	'Padding. Calculated if None.'
play_color	'00ff00'	'Text colour when playing.'
update_interval	0.5	'Update Time in seconds.'

Mpd2

`class libqtile.widget.Mpd2(**config)`

Mpd2 Object.

Parameters

status_format : format string to display status

For a full list of values, see: `MPDClient.status()` and `MPDClient.currentsong()`

https://musicpd.org/doc/protocol/command_reference.html#command_status <https://musicpd.org/doc/protocol/tags.html>

Default:

```
'{play_status} {artist}/{title} \
  [{repeat}]{random}{single}{consume}{updating_db}']
```

```play_status``` is a string from ```play_states``` dict

Note that the ```time``` property of the song renamed to ```fulltime``` to prevent conflicts with status information during formating.

**idle\_format** : format string to display status when no song is in queue.

Default:

```
'{play_status} {idle_message} \
 [{repeat}]{random}{single}{consume}{updating_db}']
```

**idle\_message** : text to display instead of song information when MPD is idle. (i.e. no song in queue)

Default:: "MPD IDLE"

**prepare\_status** : dict of functions to replace values in status with custom characters.

`f(status, key, space_element) => str`

New functionality allows use of a dictionary of plain strings.

Default:

```
status_dict = {
 'repeat': 'r',
 'random': 'z',
 'single': '1',
 'consume': 'c',
 'updating_db': 'U'
}
```

**format\_fns** : A dict of functions to format the various elements.

‘Tag’ : f(str) => str

Default:: { ‘all’: lambda s: cgi.escape(s) }

**N.B. if ‘all’ is present, it is processed on every element of song\_info** before any other formatting is done.

**mouse\_buttons** : A dict of mouse button numbers to actions

**Widget requirements: python-mpd2\_.**

**.. \_python-mpd2: <https://pypi.org/project/python-mpd2/>**

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
color_progress	None	'Text color to indicate track progress.'
command	<function default_cmd at 0x7f47af9c35f0>	'command to be executed by mapped mouse button.'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format_fns	{'all': <function escape at 0x7f47b47bb3b0>}	'Dictionary of format methods'
host	'localhost'	'Host of mpd server'
idle_format	'{play_status} {idle_message} [{repeat}{random}{single}{consume}{updating_db}]'	'format for status when mpd has no playlist.'
idle_message	'MPD IDLE'	'text to display when mpd is idle.'
idletimeout	5	'MPDClient idle command timeout'
keys	{'command': None, 'next': 5, 'previous': 4, 'stop': 3, 'toggle': 1}	'mouse button mapping. action -> b_num. deprecated.'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_buttons	{}	'b_num -> action. replaces keys.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
no_connection	'No connection'	'Text when mpd is disconnected'
padding	None	'Padding. Calculated if None.'
password	None	'Password for auth on mpd server'
play_states	{'pause': '', 'play': '', 'stop': ''}	'Play state mapping'
port	6600	'Port of mpd server'
prepare_status	{'consume': 'c', 'random': 'z', 'repeat': 'r', 'single': '1', 'updating_db': 'U'}	'characters to show the status of MPD'
space	'-'	'Space keeper'
status_format	'{play_status} {artist}/ {title} [{repeat}{random}{single}{consume}{updating_db}]'	'format for displayed song info.'
timeout	30	'MPDClient timeout'
update_interval	1	'Interval of update widget'

## Mpris2

**class** libqtile.widget.**Mpris2**(\*\**config*)

An MPRIS 2 widget

A widget which displays the current track/artist of your favorite MPRIS player. This widget scrolls the text if necessary and information that is displayed is configurable.

Widget requirements: [dbus-next](#).

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
display_metadata	['xesam:title', 'xesam:album', 'xesam:artist']	'Which metadata identifiers to display. See <a href="http://www.freedesktop.org/wiki/Specifications/mpris-spec/metadata/#index5h3">http://www.freedesktop.org/wiki/Specifications/mpris-spec/metadata/#index5h3</a> for available values'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
name	'audacious'	'Name of the MPRIS widget.'
objname	'org.mpris.MediaPlayer2.audacious'	'DBUS MPRIS 2 compatible player identifier- Find it out with dbus-monitor - Also see: <a href="http://specifications.freedesktop.org/mpris-spec/latest/#Bus-Name-Policy">http://specifications.freedesktop.org/mpris-spec/latest/#Bus-Name-Policy</a> '
padding	None	'Padding. Calculated if None.'
scroll_chars	30	'How many chars at once to display.'
scroll_interval	0.5	'Scroll delay interval.'
scroll_wait_interval	0.5	'Wait x scroll_interval before scrolling/removing text'
stop_pause_text	None	'Optional text to display when in the stopped/paused state'

## Net

**class** libqtile.widget.**Net**(\*\**config*)

Displays interface down and up speed

Widget requirements: [psutil](#).

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'{interface}: {down} ↓↑ {up}'	'Display format of down-/upload speed of given interfaces'
interface	None	'List of interfaces or single NIC as string to monitor, None to displays all active NICs combined'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
update_interval	1	'The update interval.'
use_bits	False	'Use bits instead of bytes per second?'

## NetGraph

**class** libqtile.widget.**NetGraph**(\*\**config*)

Display a network usage graph.

Widget requirements: `psutil`.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
bandwidth_type	'down'	'down(load)/up(load)'
border_color	'215578'	'Widget border color'
border_width	2	'Widget border width'
fill_color	'1667EB.3'	'Fill color for linefill graph'
frequency	1	'Update frequency in seconds'
graph_color	'18BAEB'	'Graph color'
interface	'auto'	'Interface to display info for ('auto' for detection)'
line_width	3	'Line width'
margin_x	3	'Margin X'
margin_y	3	'Margin Y'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
samples	100	'Count of graph samples.'
start_pos	'bottom'	'Drawer starting position ('bottom'/'top)'
type	'linefill'	'"box', 'line', 'linefill"'

## Notify

**class** libqtile.widget.**Notify**(width=CALCULATED, \*\*config)

A notify widget

Supported bar orientations: horizontal only

key	default	description
audiofile	None	'Audiofile played during notifications'
background	None	'Widget background color'
default_timeout	None	'Default timeout (seconds) for notifications'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
foreground_low	' dddddd '	'Foreground low priority colour'
foreground_urgent	' ff0000 '	'Foreground urgent priority colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'

## NvidiaSensors

**class** libqtile.widget.**NvidiaSensors**(\*\*config)

Displays temperature, fan speed and performance level Nvidia GPU.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
foreground_alert	' ff0000 '	'Foreground colour alert'
format	' {temp} °C '	'Display string format. Three options available: {temp} - temperature, {fan_speed} and {perf} - performance level'
gpu_bus_id	' '	'GPU's Bus ID, ex: 01:00.0. If leave empty will display all available GPU's'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
threshold	70	'If the current temperature value is above, then change to foreground_alert colour'
update_interval	2	'Update interval in seconds.'

## OpenWeather

**class** libqtile.widget.**OpenWeather**(\*\**config*)

A weather widget, data provided by the OpenWeather API.

**Some format options:**

- `location_city`
- `location_cityid`
- `location_country`
- `location_lat`
- `location_long`
- `weather`
- `weather_details`
- `units_temperature`
- `units_wind_speed`
- `isotime`
- `humidity`
- `pressure`
- `sunrise`
- `sunset`
- `temp`
- `visibility`
- `wind_speed`
- `wind_deg`
- `wind_direction`
- `weather_0_icon` # See: <https://openweathermap.org/weather-conditions>; TODO: Use icons.
- `main_feels_like`
- `main_temp_min`
- `main_temp_max`
- `clouds_all`

Supported bar orientations: horizontal only

key	default	description
app_key	'7834197c233888253f8cb4e1e140e'	API key for OpenWeatherMap. A default is provided, butn for prolonged use obtaining your own is suggested:n <a href="https://home.openweathermap.org/users/sign_up">https://home.openweathermap.org/users/sign_up</a>
background	None	'Widget background color'
cityid	None	'City ID. Can be looked up on e.g.:n <a href="https://openweathermap.org/find">https://openweathermap.org/find</a> n Takes precedence over location and coordinates.n Note that this is not equal to a WOEID.'
coordinates	None	'Dictionary containing latitude and longituden Example: coordinates={"longitude": "77.22",n "latitude": "28.67"}'
data	None	'Post Data'
dateformat	'%Y-%m-%d '	'Format for dates, defaults to ISO.n For details see: <a href="https://docs.python.org/3/library/time.html#time.strftime">https://docs.python.org/3/library/time.html#time.strftime</a>
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'{location_city} : {main_temp} °{units_temperature} {humidity}% {weather_details}'	'Display format'
headers	{}	'Extra Headers'
json	True	'Is Json?'
language	'en'	'Language of response. List of languages supported can be seen at: <a href="https://openweathermap.org/current">https://openweathermap.org/current</a> undern Multilingual support'
location	None	'Name of the city. Country name can be appendedn like cambridge,NZ. Takes precedence over zip-code.'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
metric	True	'True to use metric/C, False to use imperial/F'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
parse	None	'Parse Function'
timeformat	'%H:%M'	'Format for times, defaults to ISO.n For details see: <a href="https://docs.python.org/3/library/time.html#time.strftime">https://docs.python.org/3/library/time.html#time.strftime</a>
update_interval	600	'Update interval in seconds, if none, the widget updates whenever it's done.'
url	None	'Url'
user_agent	'Qtile'	'Set the user agent'
xml	False	'Is XML?'
zip	None	'Zip code (USA) or "zip code,country code" forn other countries. E.g. 12345,NZ. Takes precedence overn coordinates.'

## Pomodoro

**class** libqtile.widget.**Pomodoro**(*\*\*config*)

Pomodoro technique widget

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
color_active	'00ff00'	'Colour then pomodoro is running'
color_break	'ffff00'	'Colour then it is break time'
color_inactive	'ff0000'	'Colour then pomodoro is inactive'
fmt	'{'}	'fmt'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
length_long_break	15	'Length of a long break in minutes'
length_pomodori	25	'Length of one pomodori in minutes'
length_short_break	5	'Length of a short break in minutes'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
notification_on	True	'Turn notifications on'
num_pomodori	4	'Number of pomodori to do in a cycle'
padding	None	'Padding. Calculated if None.'
prefix_active	' '	'Prefix then app is active'
prefix_break	'B '	'Prefix during short break'
prefix_inactive	'POMODORO'	'Prefix when app is inactive'
prefix_long_break	'LB '	'Prefix during long break'
prefix_paused	'PAUSE'	'Prefix during pause'
update_interval	1	'Update interval in seconds, if none, the widget updates whenever the event loop is idle.'

## Prompt

**class** libqtile.widget.**Prompt**(*name='prompt', \*\*config*)

A widget that prompts for user input

Input should be started using the `.start_input()` method on this class.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
bell_style	'audible'	'Alert at the begin/end of the command history. Possible values: 'audible' (X11 only), 'visual' and None.'
cursor	True	'Show a cursor'
cursor_color	'bef098'	'Color for the cursor and text over it.'
cursorblink	0.5	'Cursor blink rate. 0 to disable.'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
ignore_dups_history	False	'Don't store duplicates in history'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
max_history	100	'Commands to keep in history. 0 for no limit.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
prompt	'{prompt}:'	'Text displayed at the prompt'
record_history	True	'Keep a record of executed commands'
visual_bell_color	'ff0000'	'Color for the visual bell (changes prompt background).'
visual_bell_time	0.2	'Visual bell duration (in seconds).'

## QuickExit

**class** libqtile.widget.**QuickExit**(*widget=CALCULATED, \*\*config*)

A button of exiting the running qtile easily. When clicked this button, a countdown start. If the button pushed with in the countdown again, the qtile shutdown.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
countdown_format	'[ {} seconds ]'	'This text is showed when counting down.'
countdown_start	5	'Time to accept the second pushing.'
default_text	'[ shutdown ]'	'A text displayed as a button'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
timer_interval	1	'A countdown interval.'

## Sep

**class** libqtile.widget.**Sep**(*height\_percent=None, \*\*config*)

A visible widget separator

Supported bar orientations: horizontal and vertical

key	default	description
background	None	'Widget background color'
foreground	'888888'	'Separator line colour.'
linewidth	1	'Width of separator line.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	2	'Padding on either side of separator.'
size_percent	80	'Size as a percentage of bar size (0-100).'

## She

**class** libqtile.widget.**She**(*\*\*config*)

Widget to display the Super Hybrid Engine status

Can display either the mode or CPU speed on eeepc computers.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
device	'/sys/devices/ platform/ eeepc/cpufv'	'sys path to cpufv'
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'speed'	'Type of info to display "speed" or "name"'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
update_interval	0.5	'Update Time in seconds.'

## Spacer

**class** libqtile.widget.**Spacer**(*length=STRETCH, width=None, \*\*config*)

Just an empty space on the bar

Often used with length equal to bar.STRETCH to push bar widgets to the right or bottom edge of the screen.

### Parameters

**length** : Length of the widget. Can be either bar.STRETCH or a length in pixels.

**width** : DEPRECATED, same as length.

Supported bar orientations: horizontal and vertical

key	default	description
background	None	'Widget background color'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'

## StockTicker

**class** libqtile.widget.**StockTicker**(\*\**config*)

A stock ticker widget, based on the alphavantage API. Users must acquire an API key from <https://www.alphavantage.co/support/#api-key>

The widget defaults to the TIME\_SERIES\_INTRADAY API function (i.e. stock symbols), but arbitrary Alpha Vantage API queries can be made by passing extra arguments to the constructor.

```
Display AMZN
widget.StockTicker(apikey=..., symbol="AMZN")

Display BTC
widget.StockTicker(apikey=..., function="DIGITAL_CURRENCY_INTRADAY", symbol="BTC",
↪market="USD")
```

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
data	None	'Post Data'
fmt	'{}'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
function	'TIME_SERIES_INTRADAY'	'Default API function to query'
headers	{}	'Extra Headers'
interval	'1min'	'The default latency to query'
json	True	'Is Json?'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
parse	None	'Parse Function'
update_interval	600	'Update interval in seconds, if none, the widget updates whenever it's done.'
url	None	'Url'
user_agent	'Qtile'	'Set the user agent'
xml	False	'Is XML?'

## SwapGraph

**class** libqtile.widget.**SwapGraph**(\*\**config*)

Display a swap info graph.

Widget requirements: `psutil`.

Supported bar orientations: horizontal only

key	default	description
<code>background</code>	<code>None</code>	'Widget background color'
<code>border_color</code>	<code>'215578'</code>	'Widget border color'
<code>border_width</code>	<code>2</code>	'Widget border width'
<code>fill_color</code>	<code>'1667EB.3'</code>	'Fill color for linefill graph'
<code>frequency</code>	<code>1</code>	'Update frequency in seconds'
<code>graph_color</code>	<code>'18BAEB'</code>	'Graph color'
<code>line_width</code>	<code>3</code>	'Line width'
<code>margin_x</code>	<code>3</code>	'Margin X'
<code>margin_y</code>	<code>3</code>	'Margin Y'
<code>mouse_callbacks</code>	<code>{}</code>	'Dict of mouse button press callback functions.'
<code>samples</code>	<code>100</code>	'Count of graph samples.'
<code>start_pos</code>	<code>'bottom'</code>	'Drawer starting position ('bottom'/'top)''
<code>type</code>	<code>'linefill'</code>	'"box', 'line', 'linefill"'

## Systray

**class** libqtile.widget.**Systray**(\*\**config*)

A widget that manages system tray.

---

**Note:** Icons will not render correctly where the bar/widget is drawn with a semi-transparent background. Instead, icons will be drawn with a transparent background.

If using this widget it is therefore recommended to use a fully opaque background colour or a fully transparent one.

---

Supported bar orientations: horizontal only

key	default	description
<code>background</code>	<code>None</code>	'Widget background color'
<code>icon_size</code>	<code>20</code>	'Icon width'
<code>mouse_callbacks</code>	<code>{}</code>	'Dict of mouse button press callback functions.'
<code>padding</code>	<code>5</code>	'Padding between icons'

## TaskList

**class** `libqtile.widget.TaskList` (\*\**config*)

Displays the icon and name of each window in the current group

Contrary to WindowTabs this is an interactive widget. The window that currently has focus is highlighted.

Supported bar orientations: horizontal only

key	default	description
<code>background</code>	None	'Widget background color'
<code>border</code>	'215578'	'Border colour'
<code>borderwidth</code>	2	'Current group border width'
<code>font</code>	'sans'	'Default font'
<code>fontshadow</code>	None	'font shadow color, default is None(no shadow)'
<code>fontsize</code>	None	'Font size. Calculated if None.'
<code>foreground</code>	'ffffff'	'Foreground colour'
<code>highlight_method</code>	'border'	"Method of highlighting (one of 'border' or 'block') Uses *_border color settings"
<code>icon_size</code>	None	'Icon size. (Calculated if set to None. Icons are hidden if set to 0.)'
<code>margin</code>	3	'Margin inside the box'
<code>margin_x</code>	None	"X Margin. Overrides 'margin' if set"
<code>margin_y</code>	None	"Y Margin. Overrides 'margin' if set"
<code>markup_floating</code>	None	'Text markup of the floating window state. Supports pangomarkup with markup=True.e.g., "{ }" or "<span underline="low">{ }</span>"'
<code>markup_focused</code>	None	'Text markup of the focused window state. Supports pangomarkup with markup=True.e.g., "{ }" or "<span underline="low">{ }</span>"'
<code>markup_maximized</code>	None	'Text markup of the maximized window state. Supports pangomarkup with markup=True.e.g., "{ }" or "<span underline="low">{ }</span>"'
<code>markup_minimized</code>	None	'Text markup of the minimized window state. Supports pangomarkup with markup=True.e.g., "{ }" or "<span underline="low">{ }</span>"'
<code>markup_normal</code>	None	'Text markup of the normal window state. Supports pangomarkup with markup=True.e.g., "{ }" or "<span underline="low">{ }</span>"'
<code>max_title_width</code>	None	'Max size in pixels of task title.(if set to None, as much as available.)'
<code>mouse_callbacks</code>	{}	'Dict of mouse button press callback functions.'
<code>padding</code>	3	'Padding inside the box'
<code>padding_x</code>	None	"X Padding. Overrides 'padding' if set"
<code>padding_y</code>	None	"Y Padding. Overrides 'padding' if set"
<code>parse_text</code>	None	'Function to parse and modify window names. e.g. function in config that removes excess strings from window name: def my_func(text) for string in [" - Chromium", " - Firefox"]: text = text.replace(string, "") return textthen set option parse_text=my_func'
<code>rounded</code>	True	'To round or not to round borders'
<code>spacing</code>	None	'Spacing between tasks.(if set to None, will be equal to margin_x)'

continues on next page

Table 2 – continued from previous page

key	default	description
title_width_method	None	“Method to compute the width of task title. (None, ‘uniform’.) Defaults to None, the normal behaviour.”
txt_floating	'V '	“Text representation of the floating window state. e.g., “V” or “”
txt_maximized	'[] '	“Text representation of the maximized window state. e.g., “[]” or “”
txt_minimized	'_ '	“Text representation of the minimized window state. e.g., “_” or “”
unfocused_border	None	“Border color for unfocused windows. Affects only highlight_method ‘border’ and ‘block’. Defaults to None, which means no special color.”
urgent_alert_method	'border'	“Method for alerting you of WM urgent hints (one of ‘border’ or ‘text’)”
urgent_border	'FF0000'	‘Urgent border color’

## TextBox

**class** libqtile.widget.**TextBox**(*text=' ', width=CALCULATED, \*\*config*)

A flexible textbox that can be updated from bound keys, scripts, and qshell.

Supported bar orientations: horizontal only

key	default	description
background	None	‘Widget background color’
fmt	'{'}	‘How to format the text’
font	'sans'	‘Text font’
fontshadow	None	‘font shadow color, default is None(no shadow)’
fontsize	None	‘Font pixel size. Calculated if None.’
foreground	'#ffffff'	‘Foreground colour.’
markup	True	‘Whether or not to use pango markup’
max_chars	0	‘Maximum number of characters to display in widget.’
mouse_callbacks	{}	‘Dict of mouse button press callback functions.’
padding	None	‘Padding left and right. Calculated if None.’

## ThermalSensor

**class** libqtile.widget.**ThermalSensor**(*\*\*config*)

Widget to display temperature sensor information

For using the thermal sensor widget you need to have lm-sensors installed. You can get a list of the tag\_sensors executing “sensors” in your terminal. Then you can choose which you want, otherwise it will display the first available.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	'{'}	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
foreground_alert	'ff0000'	'Foreground colour alert'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
metric	True	'True to use metric/C, False to use imperial/F'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
show_tag	False	'Show tag sensor'
tag_sensor	None	'Tag of the temperature sensor. For example: "temp1" or "Core 0"'
threshold	70	'If the current temperature value is above, then change to foreground_alert colour'
update_interval	2	'Update interval in seconds'

## Volume

**class** libqtile.widget.**Volume**(*\*\*config*)

Widget that display and change volume

By default, this widget uses `amixer` to get and set the volume so users will need to make sure this is installed. Alternatively, users may set the relevant parameters for the widget to use a different application.

If `theme_path` is set it draw widget as icons.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
cardid	None	'Card Id'
channel	'Master'	'Channel'
device	'default'	'Device Name'
emoji	False	'Use emoji to display volume states, only if theme_path is not set. The specified font needs to contain the correct unicode characters.'
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
get_volume_command	None	'Command to get the current volume'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
mute_command	None	'Mute command'
padding	3	'Padding left and right. Calculated if None.'
step	2	'Volume change for up and down commands in percentage. Only used if volume_up_command and volume_down_command are not set.'
theme_path	None	'Path of the icons'
update_interval	0.2	'Update time in seconds.'
volume_app	None	'App to control volume'
volume_down_command	None	'Volume down command'
volume_up_command	None	'Volume up command'

## Wallpaper

```
class libqtile.widget.Wallpaper(**config)
 Supported bar orientations: horizontal only
```

key	default	description
background	None	'Widget background color'
directory	'~/Pictures/ wallpapers/'	'Wallpaper Directory'
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
label	None	'Use a fixed label instead of image name.'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
option	'fill'	'How to fit the wallpaper when wallpaper_command is None. None, 'fill' or 'stretch.'
padding	None	'Padding. Calculated if None.'
random_selection	False	'If set, use random initial wallpaper and randomly cycle through the wallpapers.'
wallpaper	None	'Wallpaper'
wallpaper_command	['feh', '--bg-fill']	'Wallpaper command. If None, the wallpaper will be painted without the use of a helper.'

## WidgetBox

**class** libqtile.widget.**WidgetBox**(*widgets: Optional[list] = None, \*\*config*)

A widget to declutter your bar.

WidgetBox is a widget that hides widgets by default but shows them when the box is opened.

Widgets that are hidden will still update etc. as if they were on the main bar.

Button clicks are passed to widgets when they are visible so callbacks will work.

Widgets in the box also remain accessible via command interfaces.

Widgets can only be added to the box via the configuration file. The widget is configured by adding widgets to the "widgets" parameter as follows:

```
widget.WidgetBox(widgets=[
 widget.TextBox(text="This widget is in the box"),
 widget.Memory()
],
),
```

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
close_button_location	'left'	'Location of close button when box open ('left' or 'right')'
font	'sans'	'Text font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font pixel size. Calculated if None.'
foreground	'#ffffff'	'Foreground colour.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
text_closed	' [<]'	'Text when box is closed'
text_open	' [>]'	'Text when box is open'

## WindowCount

**class** libqtile.widget.**WindowCount**(*text=' ', width=CALCULATED, \*\*config*)

A simple widget to show the number of windows in the current group.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	' {}'	'How to format the text'
font	'sans'	'Text font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font pixel size. Calculated if None.'
foreground	'#ffffff'	'Foreground colour.'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding left and right. Calculated if None.'
show_zero	False	'Show window count when no windows'
text_format	' {num}'	'Format for message'

## WindowName

**class** libqtile.widget.**WindowName**(*width=STRETCH, \*\*config*)

Displays the name of the window that currently has focus

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
empty_group_string	' '	'string to display when no windows are focused on current group'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
for_current_screen	False	'instead of this bars screen use currently active screen'
foreground	' fffffff '	'Foreground colour'
format	' {state}{name} '	'format of the text'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
parse_text	None	'Function to parse and modify window names. e.g. function in config that removes excess strings from window name: def my_func(text) for string in [ " - Chromium", " - Firefox" ]: text = text.replace(string, "") return text then set option parse_text=my_func'

## WindowTabs

**class** libqtile.widget.**WindowTabs**(\*\**config*)

Displays the name of each window in the current group. Contrary to TaskList this is not an interactive widget. The window that currently has focus is highlighted.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
fmt	' {} '	'How to format the text'
font	' sans '	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	' fffffff '	'Foreground colour'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
parse_text	None	'Function to parse and modify window names. e.g. function in config that removes excess strings from window name: def my_func(text) for string in [ " - Chromium", " - Firefox" ]: text = text.replace(string, "") return text then set option parse_text=my_func'
selected	(' <b>', '</b>')	'Selected task indicator'
separator	'   '	'Task separator text.'

## Wlan

**class** libqtile.widget.**Wlan**(\*\*config)

Displays Wifi SSID and quality.

Widget requirements: `iwlib`.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
disconnected_message	'Disconnected'	'String to show when the wlan is diconnected.'
fmt	'{'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'{essid} {quality}/70'	'Display format. For percents you can use "{essid} {percent:2.0%}"'
interface	'wlan0'	'The interface to monitor'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
update_interval	1	'The update interval.'

## Wttr

**class** libqtile.widget.**Wttr**(\*\*config)

Display weather widget provided by `wttr.in`.

To specify your own custom output format, use the special `%`-notation (example: `'My_city: %t(%f), wind: %w'`):

- `%c` Weather condition,
- `%C` Weather condition textual name,
- `%h` Humidity,
- `%t` Temperature (Actual),
- `%f` Temperature (Feels Like),
- `%w` Wind,
- `%l` Location,
- `%m` Moonphase ,
- `%M` Moonday,
- `%p` precipitation (mm),
- `%P` pressure (hPa),
- `%D` Dawn !,
- `%S` Sunrise !,
- `%z` Zenith !,

- %s Sunset !,
- %d Dusk !. (!times are shown in the local timezone)

Add the character ~ at the beginning to get weather for some special location: ~Vostok Station or ~Eiffel Tower.

Also can use IP-addresses (direct) or domain names (prefixed with @) to specify a location: @github.com, 123.456.678.123

Specify multiple locations as dictionary

```
location={
 'Minsk': 'Minsk',
 '64.127146,-21.873472': 'Reykjavik',
}
```

Cities will change randomly every update.

Supported bar orientations: horizontal only

key	default	description
background	None	'Widget background color'
data	None	'Post Data'
fmt	'{}'	'How to format the text'
font	'sans'	'Default font'
fontshadow	None	'font shadow color, default is None(no shadow)'
fontsize	None	'Font size. Calculated if None.'
foreground	'ffffff'	'Foreground colour'
format	'3'	'Display text format. Choose presets in range 1-4 (Ex. "1") or build your own custom output format, use the special %-notation. See <a href="https://github.com/chubin/wtr.in#one-line-output">https://github.com/chubin/wtr.in#one-line-output</a> '
headers	{}	'Extra Headers'
json	False	'Is Json?'
lang	'en'	'Display text language. List of supported languages <a href="https://wtr.in/:translation">https://wtr.in/:translation</a> '
location	None	'Dictionary. Key is a city or place name, or GPS coordinates. Value is a display name.'
markup	True	'Whether or not to use pango markup'
max_chars	0	'Maximum number of characters to display in widget.'
mouse_callbacks	{}	'Dict of mouse button press callback functions.'
padding	None	'Padding. Calculated if None.'
parse	None	'Parse Function'
units	'm'	'"m" - metric, "M" - show wind speed in m/s, "s" - imperial'
update_interval	600	'Update interval in seconds. Recommendation: if you want to display multiple locations alternately, maybe set a smaller interval, ex. 30.'
url	None	'Url'
user_agent	'Qtile'	'Set the user agent'
xml	False	'Is XML?'

## 1.5.4 Built-in Extensions

### CommandSet

**class** libqtile.extension.**CommandSet**(*\*\*config*)

Give list of commands to be executed in dmenu style.

ex. manage mocp daemon:

```
Key([mod], 'm', lazy.run_extension(extension.CommandSet(
 commands={
 'play/pause': '[$(mocp -i | wc -l) -lt 2] && mocp -p || mocp -G',
 'next': 'mocp -f',
 'previous': 'mocp -r',
 'quit': 'mocp -x',
 'open': 'urxvt -e mocp',
 'shuffle': 'mocp -t shuffle',
 'repeat': 'mocp -t repeat',
 },
 pre_commands=['[$(mocp -i | wc -l) -lt 1] && mocp -S'],
 **Theme.dmenu)))
```

key	default	description
background	None	'defines the normal background color'
command	None	'the command to be launched (string or list with arguments)'
commands	None	'dictionary of commands where key is runnable command'
dmenu_bottom	False	'dmenu appears at the bottom of the screen'
dmenu_command	'dmenu'	'the dmenu command to be launched'
dmenu_font	None	"override the default 'font' and 'fontsize' options for dmenu"
dmenu_height	None	'defines the height (only supported by some dmenu forks)'
dmenu_ignorecase	False	'dmenu matches menu items case insensitively'
dmenu_lines	None	'dmenu lists items vertically, with the given number of lines'
dmenu_prompt	None	'defines the prompt to be displayed to the left of the input field'
font	'sans'	'defines the font name to be used'
fontsize	None	'defines the font size to be used'
foreground	None	'defines the normal foreground color'
pre_commands	None	'list of commands to be executed before getting dmenu answer'
selected_background	None	'defines the selected background color'
selected_foreground	None	'defines the selected foreground color'

## Dmenu

`class libqtile.extension.Dmenu(**config)`

Python wrapper for dmenu <http://tools.suckless.org/dmenu/>

key	default	description
background	None	'defines the normal background color'
command	None	'the command to be launched (string or list with arguments)'
dmenu_bottom	False	'dmenu appears at the bottom of the screen'
dmenu_command	'dmenu'	'the dmenu command to be launched'
dmenu_font	None	"override the default 'font' and 'fontsize' options for dmenu"
dmenu_height	None	'defines the height (only supported by some dmenu forks)'
dmenu_ignorecase	False	'dmenu matches menu items case insensitively'
dmenu_lines	None	'dmenu lists items vertically, with the given number of lines'
dmenu_prompt	None	'defines the prompt to be displayed to the left of the input field'
font	'sans'	'defines the font name to be used'
fontsize	None	'defines the font size to be used'
foreground	None	'defines the normal foreground color'
selected_background	None	'defines the selected background color'
selected_foreground	None	'defines the selected foreground color'

## DmenuRun

`class libqtile.extension.DmenuRun(**config)`

Special case to run applications.

config.py should have something like:

```
from libqtile import extension
keys = [
 Key(['mod4'], 'r', lazy.run_extension(extension.DmenuRun(
 dmenu_prompt=">",
 dmenu_font="Andika-8",
 background="#15181a",
 foreground="#00ff00",
 selected_background="#079822",
 selected_foreground="#fff",
 dmenu_height=24, # Only supported by some dmenu forks
))),
]
```

key	default	description
background	None	'defines the normal background color'
command	None	'the command to be launched (string or list with arguments)'
dmenu_bottom	False	'dmenu appears at the bottom of the screen'
dmenu_command	'dmenu_run'	'the dmenu command to be launched'
dmenu_font	None	'override the default 'font' and 'fontsize' options for dmenu'
dmenu_height	None	'defines the height (only supported by some dmenu forks)'
dmenu_ignorecase	False	'dmenu matches menu items case insensitively'
dmenu_lines	None	'dmenu lists items vertically, with the given number of lines'
dmenu_prompt	None	'defines the prompt to be displayed to the left of the input field'
font	'sans'	'defines the font name to be used'
fontsize	None	'defines the font size to be used'
foreground	None	'defines the normal foreground color'
selected_background	None	'defines the selected background color'
selected_foreground	None	'defines the selected foreground color'

## J4DmenuDesktop

`class libqtile.extension.J4DmenuDesktop(**config)`

Python wrapper for j4-dmenu-desktop <https://github.com/enkore/j4-dmenu-desktop>

key	default	description
background	None	'defines the normal background color'
command	None	'the command to be launched (string or list with arguments)'
dmenu_bottom	False	'dmenu appears at the bottom of the screen'
dmenu_command	'dmenu'	'the dmenu command to be launched'
dmenu_font	None	'override the default 'font' and 'fontsize' options for dmenu'
dmenu_height	None	'defines the height (only supported by some dmenu forks)'
dmenu_ignorecase	False	'dmenu matches menu items case insensitively'
dmenu_lines	None	'dmenu lists items vertically, with the given number of lines'
dmenu_prompt	None	'defines the prompt to be displayed to the left of the input field'
font	'sans'	'defines the font name to be used'
fontsize	None	'defines the font size to be used'
foreground	None	'defines the normal foreground color'
j4dmenu_command	'j4-dmenu-desktop'	'the dmenu command to be launched'
j4dmenu_display_binary	False	'display binary name after each entry'
j4dmenu_generic	True	'include the generic name of desktop entries'
j4dmenu_terminal	None	'terminal emulator used to start terminal apps'
j4dmenu_usage_log	None	'file used to sort items by usage frequency'
j4dmenu_use_xdg_desktop	False	'read \$XDG_CURRENT_DESKTOP to determine the desktop environment'
selected_background	None	'defines the selected background color'
selected_foreground	None	'defines the selected foreground color'

## RunCommand

**class** libqtile.extension.**RunCommand**(\*\*config)

Run an arbitrary command.

Mostly useful as a superclass for more specific extensions that need to interact with the qtile object.

Also consider simply using lazy.spawn() or writing a [client](#).

key	default	description
background	None	'defines the normal background color'
command	None	'the command to be launched (string or list with arguments)'
font	'sans'	'defines the font name to be used'
fontsize	None	'defines the font size to be used'
foreground	None	'defines the normal foreground color'
selected_background	None	'defines the selected background color'
selected_foreground	None	'defines the selected foreground color'

## WindowList

**class** libqtile.extension.**WindowList**(\*\*config)

Give vertical list of all open windows in dmenu. Switch to selected.

key	default	description
all_groups	True	'If True, list windows from all groups; otherwise only from the current group'
background	None	'defines the normal background color'
command	None	'the command to be launched (string or list with arguments)'
dmenu_bottom	False	'dmenu appears at the bottom of the screen'
dmenu_command	'dmenu'	'the dmenu command to be launched'
dmenu_font	None	'override the default 'font' and 'fontsize' options for dmenu'
dmenu_height	None	'defines the height (only supported by some dmenu forks)'
dmenu_ignorecase	False	'dmenu matches menu items case insensitively'
dmenu_lines	'80'	'Give lines vertically. Set to None get inline'
dmenu_prompt	None	'defines the prompt to be displayed to the left of the input field'
font	'sans'	'defines the font name to be used'
fontsize	None	'defines the font size to be used'
foreground	None	'defines the normal foreground color'
item_format	'{group}. {id}: {window}'	'the format for the menu items'
selected_background	None	'defines the selected background color'
selected_foreground	None	'defines the selected foreground color'



## ADVANCED SCRIPTING

### 2.1 Scripting

#### 2.1.1 Client-Server Scripting Model

Qtile has a client-server control model - the main Qtile instance listens on a named pipe, over which marshalled command calls and response data is passed. This allows Qtile to be controlled fully from external scripts. Remote interaction occurs through an instance of the `libqtile.command.interface.IPCCommandInterface` class. This class establishes a connection to the currently running instance of Qtile. A `libqtile.command.client.CommandClient` can use this connection to dispatch commands to the running instance. Commands then appear as methods with the appropriate signature on the `CommandClient` object. The object hierarchy is described in the *Commands API* section of this manual. Full command documentation is available through the *Qtile Shell*.

#### 2.1.2 Example

Below is a very minimal example script that inspects the current Qtile instance, and returns the integer offset of the current screen.

```
from libqtile.command.client import CommandClient
c = CommandClient()
print(c.screen.info()["index"])
```

### 2.2 Commands API


Qtile's command API is based on a graph of objects, where each object has a set of associated commands. The graph and object commands are used in a number of different places:

- Commands can be *bound to keys* in the Qtile configuration file.
- Commands can be *called through qtile shell*, the Qtile shell.
- The qsh can also be hooked into a Jupyter kernel *called iqshell*.
- Commands can be *called from a script* to interact with Qtile from Python.

If the explanation below seems a bit complex, please take a moment to explore the API using the `qtile shell` command shell. Command lists and detailed documentation can be accessed from its built-in help command.

## 2.2.1 Introduction: Object Graph

The objects in Qtile’s object graph come in seven flavours, matching the seven basic components of the window manager: layouts, windows, groups, bars, widgets, screens, and a special root node. Objects are addressed by a path specification that starts at the root, and follows the edges of the graph. This is what the graph looks like:



Each arrow can be read as “holds a reference to”. So, we can see that a `widget` object *holds a reference to* objects of type `bar`, `screen` and `group`. Lets start with some simple examples of how the addressing works. Which particular objects we hold reference to depends on the context - for instance, widgets hold a reference to the screen that they appear on, and the bar they are attached to.

Lets look at an example, starting at the root node. The following script runs the `status` command on the root node, which, in this case, is represented by the `InteractiveCommandClient` object:

```
from libqtile.command.client import InteractiveCommandClient
c = InteractiveCommandClient()
print(c.status())
```

The `InteractiveCommandClient` is a class that allows us to traverse the command graph using attributes to select child nodes or commands. In this example, we have resolved the `status()` command on the root object. The interactive command client will automatically find and connect to a running Qtile instance, and which it will use to dispatch the call and print out the return.

An alternative is to use the `CommandClient`, which allows for a more precise resolution of command graph objects, but is not as easy to interact with from a REPL:

```
from libqtile.command.client import CommandClient
c = CommandClient()
print(c.call("status")())
```

Like the interactive client, the command client will automatically connect to a running Qtile instance. Here, we first resolve the `status()` command with the `.call("status")`, which simply located the function, then we can invoke the call with no arguments.

For the rest of this example, we will use the interactive command client. From the graph, we can see that the root node holds a reference to group nodes. We can access the “info” command on the current group like so:

```
c.group.info()
```

To access a specific group, regardless of whether or not it is current, we use the Python mapping lookup syntax. This command sends group “b” to screen 1 (by the `libqtile.config.Group.to_screen()` method):

```
c.group["b"].to_screen(1)
```

In different contexts, it is possible to access a default object, where in other contexts a key is required. From the root of the graph, the current `group`, `layout`, `screen` and `window` can be accessed by simply leaving the key specifier out. The key specifier is mandatory for `widget` and `bar` nodes.

With this context, we can now drill down deeper in the graph, following the edges in the graphic above. To access the screen currently displaying group “b”, we can do this:

```
c.group["b"].screen.info()
```

Be aware, however, that group “b” might not currently be displayed. In that case, it has no associated screen, the path resolves to a non-existent node, and we get an exception:

```
libqtile.command.CommandError: No object screen in path 'group['b'].screen'
```

The graph is not a tree, since it can contain cycles. This path (redundantly) specifies the group belonging to the screen that belongs to group “b”:

```
c.group["b"].screen.group
```

This amount of connectivity makes it easy to reach out from a given object when callbacks and events fire on that object to related objects.

## 2.2.2 Keys

The key specifier for the various object types are as follows:

Object	Key	Optional?	Example
bar	“top”, “bottom”	No	<code>c.screen.bar[“bottom”]</code>
group	Name string	Yes	<code>c.group[“one”]</code> <code>c.group</code>
layout	Integer index	Yes	<code>c.layout[2]</code> <code>c.layout</code>
screen	Integer index	Yes	<code>c.screen[1]</code> <code>c.screen</code>
widget	Widget name	No	<code>c.widget[“textbox”]</code>
window	Integer window ID	Yes	<code>c.window[123456]</code> <code>c.window</code>

## 2.2.3 Digging Deeper: Command Objects

If you just want to script your Qtile window manager the above information, in addition to the documentation on the *various scripting commands* should be enough to get started. To develop the Qtile manager itself, we can dig into how Qtile represents these objects, which will lead to the way the commands are dispatched.

All of the configured objects setup by Qtile are `CommandObject` subclasses. These objects are so named because we can issue commands against them using the command scripting API. Looking through the code, the commands that are exposed are commands named `cmd_*`. When writing custom layouts, widgets, or any other object, you can add your own custom `cmd_` functions and they will be callable using the standard command infrastructure. An available command can be extracted by calling `.command()` with the name of the command.

In addition to having a set of associated commands, each command object also has a collection of items associated with it. This is what forms the graph that is shown above. For a given object type, the `items()` method returns all of the names of the associated objects of that type and whether or not there is a defaultable value. For example, from the root, `.items("group")` returns the name of all of the groups and that there is a default value, the currently focused group.

To navigate from one command object to the next, the `.select()` method is used. This method resolves a requested object from the command graph by iteratively selecting objects. A selector like `[("group", "b"), ("screen", None)]` would be to first resolve group “b”, then the screen associated to the group.

## 2.2.4 The Command Graph

In order to help in specifying command objects, there is the abstract command graph structure. The command graph structure allows us to address any valid command object and issue any command against it without needing to have any Qtile instance running or have anything to resolve the objects to. This is particularly useful when constructing lazy calls, where the Qtile instance does not exist to specify the path that will be resolved when the command is executed. The only limitation of traversing the command graph is that it must follow the allowed edges specified in the first section above.

Every object in the command graph is represented by a `CommandGraphNode`. Any call can be resolved from a given node. In addition, each node knows about all of the children objects that can be reached from it and have the ability to `.navigate()` to the other nodes in the command graph. Each of the object types are represented as `CommandGraphObject` types and the root node of the graph, the `CommandGraphRoot` represents the Qtile instance. When a call is performed on an object, it returns a `CommandGraphCall`. Each call will know its own name as well as be able to resolve the path through the command graph to be able to find itself.

Note that the command graph itself can stand alone, there is no other functionality within Qtile that it relies on. While we could have started here and built up, it is helpful to understand the objects that the graph is meant to represent, as the graph is just a representation of a traversal of the real objects in a running Qtile window manager. In order to tie the running Qtile instance to the abstract command graph, we move on to the command interface.

## 2.2.5 Executing graph commands: Command Interface

The `CommandInterface` is what lets us take an abstract call on the command graph and resolve it against a running command object. Put another way, this is what takes the graph traversal `.group["b"].screen.info()` and executes the `info()` command against the addressed `screen` object. Additional functionality can be used to check that a given traversal resolves to actual objects and that the requested command actually exists. Note that by construction of the command graph, the traversals here must be feasible, even if they cannot be resolved for a given configuration state. For example, it is possible to check the screen associated to a group, even though the group may not be on a screen, but it is not possible to check the widget associated to a group.

The simplest form of the command interface is the `QtileCommandInterface`, which can take an in-process Qtile instance as the root `CommandObject` and execute requested commands. This is typically how we run the unit tests for Qtile.

The other primary example of this is the `IPCCommandInterface` which is able to then route all calls through an IPC client connected to a running Qtile instance. In this case, the command graph call can be constructed on the client side without having to dispatch to Qtile and once the call is constructed and deemed valid, the call can be executed.

In both of these cases, executing a command on a command interface will return the result of executing the command on a running Qtile instance. To support lazy execution, the `LazyCommandInterface` instead returns a `LazyCall` which is able to be resolved later by the running Qtile instance when it is configured to fire.

## 2.2.6 Tying it together: Command Client

So far, we have our running Command Objects and the Command Interface to dispatch commands against these objects as well as the Command Graph structure itself which encodes how to traverse the connections between the objects. The final component which ties everything together is the Command Client, which allows us to navigate through the graph to resolve objects, find their associated commands, and execute the commands against the held command interface.

The idea of the command client is that it is created with a reference into the command graph and a command interface. All navigation can be done against the command graph, and traversal is done by creating a new command client starting from the new node. When a command is executed against a node, that command is dispatched to the held command interface. The key decision here is how to perform the traversal. The command client exists in two different flavors: the standard `CommandClient` which is useful for handling more programmatic traversal of the graph, calling methods to

traverse the graph, and the `InteractiveCommandClient` which behaves more like a standard Python object, traversing by accessing properties and performing key lookups.

Returning to our examples above, we now have the full context to see what is going on when we call:

```
from libqtile.command.client import CommandClient
c = CommandClient()
print(c.call("status")())
from libqtile.command.client import InteractiveCommandClient
c = InteractiveCommandClient()
print(c.status())
```

In both cases, the command clients are constructed with the default command interface, which sets up an IPC connection to the running Qtile instance, and starts the client at the graph root. When we call `c.call("status")` or `c.status`, we navigate the command client to the `status` command on the root graph object. When these are invoked, the commands graph calls are dispatched via the IPC command interface and the results then sent back and printed on the local command line.

The power that can be realized by separating out the traversal and resolution of objects in the command graph from actually invoking or looking up any objects within the graph can be seen in the `lazy` module. By creating a lazy evaluated command client, we can expose the graph traversal and object resolution functionality via the same `InteractiveCommandClient` that is used to perform live command execution in the Qtile prompt.

## 2.3 Scripting Commands

Here is documented some of the commands available on objects in the command tree when running `qshell` or scripting commands to `qtile`. Note that this is an incomplete list, some objects, such as *layouts* and *widgets*, may implement their own set of commands beyond those given here.

### 2.3.1 Qtile

```
class libqtile.core.manager.Qtile(kore: base.Core, config, no_spawn: bool = False, state: Optional[str] = None, socket_path: Optional[str] = None)
```

This object is the *root* of the command graph

```
cmd_add_rule(match_args: Dict[str, Any], rule_args: Dict[str, Any], min_priority: bool = False)
 Add a dgroup rule, returns rule_id needed to remove it
```

#### Parameters

**match\_args** : `config.Match` arguments

**rule\_args** : `config.Rule` arguments

**min\_priority** : If the rule is added with minimum priority (last) (default: `False`)

```
cmd_addgroup(group: str, label: Optional[str] = None, layout: Optional[str] = None, layouts: Optional[List[Layout]] = None) → bool
```

Add a group with the given name

```
cmd_change_vt(vt: int) → bool
```

Change virtual terminal, returning success.

```
cmd_commands() → List[str]
```

Returns a list of possible commands for this object

Used by `__qsh__` for command completion and online help

**cmd\_critical()** → None  
Set log level to CRITICAL

**cmd\_debug()** → None  
Set log level to DEBUG

**cmd\_delgroup**(*group: str*) → None  
Delete a group with the given name

**cmd\_display\_kb**(\**args*) → str  
Display table of key bindings

**cmd\_doc**(*name*) → str  
Returns the documentation for a specified command name  
Used by `__qsh__` to provide online help.

**cmd\_error()** → None  
Set log level to ERROR

**cmd\_eval**(*code: str*) → Tuple[bool, Optional[str]]  
Evaluates code in the same context as this function

Return value is tuple (*success, result*), *success* being a boolean and *result* being a string representing the return value of `eval`, or `None` if `exec` was used instead.

**cmd\_findwindow**(*prompt: str = 'window', widget: str = 'prompt'*) → None  
Launch prompt widget to find a window of the given name

#### Parameters

**prompt** : Text with which to prompt user (default: “window”)

**widget** : Name of the prompt widget (default: “prompt”)

**cmd\_function**(*function, \*args, \*\*kwargs*) → None  
Call a function with current object as argument

**cmd\_get\_state**() → str  
Get pickled state for restarting qtile

**cmd\_get\_test\_data**() → Any  
Returns any content arbitrarily set in the `self.test_data` attribute. Useful in tests.

**cmd\_groups**() → Dict[str, Dict[str, Any]]  
Return a dictionary containing information for all groups

#### Examples

```
groups()
```

**cmd\_hide\_show\_bar**(*position: Literal['top', 'bottom', 'left', 'right', 'all'] = 'all'*) → None  
Toggle visibility of a given bar

#### Parameters

**position** : one of: “top”, “bottom”, “left”, “right”, or “all” (default: “all”)

**cmd\_info**() → None  
Set log level to INFO

**cmd\_internal\_windows**() → List[Dict[str, Any]]  
Return info for each internal window (bars, for example)

**cmd\_items**(*name*) → Tuple[bool, Optional[List[Union[str, int]]]]

Returns a list of contained items for the specified name

Used by `__qsh__` to allow navigation of the object graph.

**cmd\_labelgroup**(*prompt: str = 'label', widget: str = 'prompt'*) → None

Launch prompt widget to label the current group

#### Parameters

**prompt** : Text with which to prompt user (default: “label”)

**widget** : Name of the prompt widget (default: “prompt”)

**cmd\_list\_widgets**() → List[str]

List of all addressible widget names

**cmd\_loglevel**() → int

**cmd\_loglevelname**() → str

**cmd\_next\_layout**(*name: Optional[str] = None*) → None

Switch to the next layout.

#### Parameters

**name** : Group name. If not specified, the current group is assumed

**cmd\_next\_screen**() → None

Move to next screen

**cmd\_next\_urgent**() → None

Focus next window with urgent hint

**cmd\_pause**() → None

Drops into pdb

**cmd\_prev\_layout**(*name: Optional[str] = None*) → None

Switch to the previous layout.

#### Parameters

**name** : Group name. If not specified, the current group is assumed

**cmd\_prev\_screen**() → None

Move to the previous screen

**cmd\_qtile\_info**() → Dict

Returns a dictionary of info on the Qtile instance

**cmd\_qtilecmd**(*prompt: str = 'command', widget: str = 'prompt', messenger: str = 'xmessage'*) → None

Execute a Qtile command using the client syntax

Tab completion aids navigation of the command tree

#### Parameters

**prompt** : Text to display at the prompt (default: “command: “)

**widget** : Name of the prompt widget (default: “prompt”)

**messenger** : Command to display output, set this to None to disable (default: “xmessage”)

**cmd\_reconfigure\_screens**(*ev: Any = None*) → None

This can be used to set up screens again during run time. Intended usage is to be called when the `screen_change` hook is fired, responding to changes in physical monitor setup by configuring `qtile.screens` accordingly. The `ev` kwarg is ignored; it is here in case this function is hooked directly to `screen_change`.

**cmd\_remove\_rule**(*rule\_id: int*) → None

Remove a dgroup rule by `rule_id`

**cmd\_restart**() → None

Restart qtile

**cmd\_run\_extension**(*extension: libqtile.extension.base.\_Extension*) → None

Run extensions

**cmd\_screens**() → List[Dict[str, Any]]

Return a list of dictionaries providing information on all screens

**cmd\_shutdown**() → None

Quit Qtile

**cmd\_simulate\_keypress**(*modifiers, key*) → None

Simulates a keypress on the focused window.

#### Parameters

**modifiers** : A list of modifier specification strings. Modifiers can be one of “shift”, “lock”, “control” and “mod1” - “mod5”.

**key** : Key specification.

#### Examples

```
simulate_keypress(["control", "mod2"], "k")
```

**cmd\_spawn**(*cmd: Union[str, List[str]], shell: bool = False*) → int

Run `cmd`, in a shell or not (default).

`cmd` may be a string or a list (similar to `subprocess.Popen`).

#### Examples

```
spawn("firefox")
```

```
spawn(["xterm", "-T", "Temporary terminal"])
```

**cmd\_spawncmd**(*prompt: str = 'spawn', widget: str = 'prompt', command: str = '%s', complete: str = 'cmd', shell: bool = True*) → None

Spawn a command using a prompt widget, with tab-completion.

#### Parameters

**prompt** : Text with which to prompt user (default: “spawn: “).

**widget** : Name of the prompt widget (default: “prompt”).

**command** : command template (default: “%s”).

**complete** : Tab completion function (default: “cmd”)

**cmd\_status**() → Literal[‘OK’]

Return “OK” if Qtile is running

**cmd\_switch\_groups**(*namea: str, nameb: str*) → None

Switch position of two groups by name

**cmd\_switchgroup**(*prompt: str = 'group', widget: str = 'prompt'*) → None

Launch prompt widget to switch to a given group to the current screen

#### Parameters

**prompt** : Text with which to prompt user (default: “group”)

**widget** : Name of the prompt widget (default: “prompt”)

**cmd\_sync**() → None

Sync the backend’s event queue. Should only be used for development.

**cmd\_to\_layout\_index**(*index: str, name: Optional[str] = None*) → None

Switch to the layout with the given index in self.layouts.

#### Parameters

**index** : Index of the layout in the list of layouts.

**name** : Group name. If not specified, the current group is assumed.

**cmd\_to\_screen**(*n: int*) → None

Warp focus to screen n, where n is a 0-based screen number

### Examples

```
to_screen(0)
```

**cmd\_togroup**(*prompt: str = 'group', widget: str = 'prompt'*) → None

Launch prompt widget to move current window to a given group

#### Parameters

**prompt** : Text with which to prompt user (default: “group”)

**widget** : Name of the prompt widget (default: “prompt”)

**cmd\_tracemalloc\_dump**() → Tuple[bool, str]

Dump tracemalloc snapshot

**cmd\_tracemalloc\_toggle**() → None

Toggle tracemalloc status

Running tracemalloc is required for *qtile top*

**cmd\_ungrab\_all\_chords**() → None

Leave all chord modes and grab the root bindings

**cmd\_ungrab\_chord**() → None

Leave a chord mode

**cmd\_validate\_config**() → None

**cmd\_warning**() → None

Set log level to WARNING

**cmd\_windows**() → List[Dict[str, Any]]

Return info for each client window

## 2.3.2 Bar

**class** `libqtile.bar.Bar(widgets, size, **config)`

A bar, which can contain widgets

### Parameters

**widgets** : A list of widget objects.

**size** : The “thickness” of the bar, i.e. the height of a horizontal bar, or the width of a vertical bar.

key	default	description
<code>background</code>	<code>'#000000'</code>	‘Background colour.’
<code>margin</code>	<code>0</code>	‘Space around bar as int or list of ints [N E S W].’
<code>opacity</code>	<code>1</code>	‘Bar window opacity.’

**cmd\_commands()** → `List[str]`

Returns a list of possible commands for this object

Used by `__qsh__` for command completion and online help

**cmd\_doc(name)** → `str`

Returns the documentation for a specified command name

Used by `__qsh__` to provide online help.

**cmd\_eval(code: str)** → `Tuple[bool, Optional[str]]`

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), *success* being a boolean and *result* being a string representing the return value of `eval`, or `None` if `exec` was used instead.

**cmd\_fake\_button\_press(screen, position, x, y, button=1)**

Fake a mouse-button-press on the bar. Co-ordinates are relative to the top-left corner of the bar.

:screen The integer screen offset :position One of “top”, “bottom”, “left”, or “right”

**cmd\_function(function, \*args, *\*\*kwargs*)** → `None`

Call a function with current object as argument

**cmd\_info()**

Info for this object.

**cmd\_items(name)** → `Tuple[bool, Optional[List[Union[str, int]]]]`

Returns a list of contained items for the specified name

Used by `__qsh__` to allow navigation of the object graph.

## 2.3.3 Group

**class** `libqtile.config.Group(name: str, matches: Optional[List[libqtile.config.Match]] = None, exclusive=False, spawn: Optional[Union[str, List[str]]] = None, layout: Optional[str] = None, layouts: Optional[List] = None, persist=True, init=True, layout_opts=None, screen_affinity=None, position=9223372036854775807, label: Optional[str] = None)`

Represents a “dynamic” group

These groups can spawn apps, only allow certain Matched windows to be on them, hide when they’re not in use, etc. Groups are identified by their name.

## Parameters

- name: string** the name of this group
- matches: default ``None``** list of `Match` objects whose windows will be assigned to this group
- exclusive: boolean** when other apps are started in this group, should we allow them here or not?
- spawn: string or list of strings** this will be `exec()` d when the group is created, you can pass either a program name or a list of programs to `exec()`
- layout: string** the name of default layout for this group (e.g. 'max' or 'stack'). This is the name specified for a particular layout in `config.py` or if not defined it defaults in general the class name in all lower case.
- layouts: list** the group layouts list overriding global layouts. Use this to define a separate list of layouts for this particular group.
- persist: boolean** should this group stay alive with no member windows?
- init: boolean** is this group alive when qtile starts?
- position int** group position
- label: string** the display name of the group. Use this to define a display name other than name of the group. If set to `None`, the display name is set to the name.

## 2.3.4 Screen

```
class libqtile.config.Screen(top: Optional[Union[libqtile.bar.Bar, libqtile.bar.Gap]] = None, bottom:
 Optional[Union[libqtile.bar.Bar, libqtile.bar.Gap]] = None, left:
 Optional[Union[libqtile.bar.Bar, libqtile.bar.Gap]] = None, right:
 Optional[Union[libqtile.bar.Bar, libqtile.bar.Gap]] = None, wallpaper:
 Optional[str] = None, wallpaper_mode: Optional[str] = None, x:
 Optional[int] = None, y: Optional[int] = None, width: Optional[int] = None,
 height: Optional[int] = None)
```

A physical screen, and its associated paraphernalia.

Define a screen with a given set of Bars of a specific geometry. Note that `bar.Bar` objects can only be placed at the top or the bottom of the screen (`bar.Gap` objects can be placed anywhere). Also, `x`, `y`, `width`, and `height` aren't specified usually unless you are using 'fake screens'.

The `wallpaper` parameter, if given, should be a path to an image file. How this image is painted to the screen is specified by the `wallpaper_mode` parameter. By default, the image will be placed at the screens origin and retain its own dimensions. If the mode is 'fill', the image will be centred on the screen and resized to fill it. If the mode is 'stretch', the image is stretched to fit all of it into the screen.

**cmd\_commands()** → List[str]

Returns a list of possible commands for this object

Used by `__qsh__` for command completion and online help

**cmd\_doc(name)** → str

Returns the documentation for a specified command name

Used by `__qsh__` to provide online help.

**cmd\_eval(code: str)** → Tuple[bool, Optional[str]]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), *success* being a boolean and *result* being a string representing the return value of `eval`, or `None` if `exec` was used instead.

**cmd\_function**(*function*, \**args*, \*\**kwargs*) → None  
Call a function with current object as argument

**cmd\_info**()  
Returns a dictionary of info for this screen.

**cmd\_items**(*name*) → Tuple[bool, Optional[List[Union[str, int]]]]  
Returns a list of contained items for the specified name  
  
Used by `__qsh__` to allow navigation of the object graph.

**cmd\_next\_group**(*skip\_empty=False*, *skip\_managed=False*)  
Switch to the next group

**cmd\_prev\_group**(*skip\_empty=False*, *skip\_managed=False*, *warp=True*)  
Switch to the previous group

**cmd\_resize**(*x=None*, *y=None*, *w=None*, *h=None*)  
Resize the screen

**cmd\_toggle\_group**(*group\_name=None*, *warp=True*)  
Switch to the selected group or to the previously active one

**cmd\_togglegroup**(*groupName=None*)  
Switch to the selected group or to the previously active one  
  
Deprecated: use `toggle_group()`

### 2.3.5 Window

`class libqtile.backend.x11.window.Window(window, qtile)`

**cmd\_bring\_to\_front**()  
Bring the window to the front

**cmd\_commands**() → List[str]  
Returns a list of possible commands for this object  
  
Used by `__qsh__` for command completion and online help

**cmd\_disable\_floating**()  
Tile the window.

**cmd\_disable\_fullscreen**()  
Un-fullscreen the window

**cmd\_doc**(*name*) → str  
Returns the documentation for a specified command name  
  
Used by `__qsh__` to provide online help.

**cmd\_down\_opacity**()  
Decrease the window's opacity

**cmd\_enable\_floating**()  
Float the window.

**cmd\_enable\_fullscreen**()  
Fullscreen the window

**cmd\_eval**(*code: str*) → Tuple[bool, Optional[str]]  
Evaluates code in the same context as this function  
Return value is tuple (*success, result*), *success* being a boolean and *result* being a string representing the return value of *eval*, or *None* if *exec* was used instead.

**cmd\_focus**(*warp: bool = True*) → None  
Focuses the window.

**cmd\_function**(*function, \*args, \*\*kwargs*) → None  
Call a function with current object as argument

**cmd\_get\_position**()  
Get the (x, y) of the window

**cmd\_get\_size**()  
Get the (width, height) of the window

**cmd\_hints**()  
Returns the X11 hints (WM\_HINTS and WM\_SIZE\_HINTS) for this window.

**cmd\_info**()  
Returns a dictionary of info for this object

**cmd\_inspect**()  
Tells you more than you ever wanted to know about a window

**cmd\_items**(*name*) → Tuple[bool, Optional[List[Union[str, int]]]]  
Returns a list of contained items for the specified name  
Used by `__qsh__` to allow navigation of the object graph.

**cmd\_kill**()  
Kill this window  
Try to do this politely if the client support this, otherwise be brutal.

**cmd\_match**(*\*args, \*\*kwargs*)

**cmd\_move\_floating**(*dx, dy*)  
Move window by dx and dy

**cmd\_opacity**(*opacity*)  
Set the window's opacity

**cmd\_place**(*x, y, width, height, borderwidth, bordercolor, above=False, margin=None*)  
Place the window with the given position and geometry.

**cmd\_resize\_floating**(*dw, dh*)  
Add dw and dh to size of window

**cmd\_set\_position**(*x, y*)

**cmd\_set\_position\_floating**(*x, y*)  
Move window to x and y

**cmd\_set\_size\_floating**(*w, h*)  
Set window dimensions to w and h

**cmd\_static**(*screen=None, x=None, y=None, width=None, height=None*)  
Makes this window a static window, attached to a Screen

If any of the arguments are left unspecified, the values given by the window itself are used instead. So, for a window that's aware of its appropriate size and location (like dzen), you don't have to specify anything.

**cmd\_toggle\_floating()**

Toggle the floating state of the window.

**cmd\_toggle\_fullscreen()**

Toggle the fullscreen state of the window.

**cmd\_toggle\_maximize()**

Toggle the fullscreen state of the window.

**cmd\_toggle\_minimize()****cmd\_togroup(*groupName=None*, \*, *switch\_group=False*)**

Move window to a specified group.

If *groupName* is not specified, we assume the current group. If *switch\_group* is True, also switch to that group.

**Examples**

Move window to current group:

```
togroup()
```

Move window to group "a":

```
togroup("a")
```

Move window to group "a", and switch to group "a":

```
togroup("a", switch_group=True)
```

**cmd\_toscreen(*index=None*)**

Move window to a specified screen.

If *index* is not specified, we assume the current screen

**Examples**

Move window to current screen:

```
toscreen()
```

Move window to screen 0:


```
toscreen(0)
```

**cmd\_up\_opacity()**

Increase the window's opacity


## 2.4 Keybindings in images

### 2.4.1 Default configuration




## Qtile Keybindings for Qtile

Modifiers: mod4, shift



## Qtile Keybindings for Qtile

Modifiers: mod4, control



## 2.4.2 Generate your own images

Qtile provides a tiny helper script to generate keybindings images from a config file. In the repository, the script is located under `scripts/gen-keybinding-img`.

This script accepts a configuration file and an output directory. If no argument is given, the default configuration will be used and files will be placed in same directory where the command has been run.

```
usage: gen-keybinding-img [-h] [-c CONFIGFILE] [-o OUTPUT_DIR]
```

Qtile keybindings image generator

optional arguments:

```
-h, --help show this help message and exit
-c CONFIGFILE, --config CONFIGFILE
 use specified configuration file. If no presented
 default will be used
-o OUTPUT_DIR, --output-dir OUTPUT_DIR
 set directory to export all images to
```

## GETTING INVOLVED

### 3.1 Contributing

#### 3.1.1 Reporting bugs

Perhaps the easiest way to contribute to Qtile is to report any bugs you run into on the [GitHub issue tracker](#).

Useful bug reports are ones that get bugs fixed. A useful bug report normally has two qualities:

1. **Reproducible.** If your bug is not reproducible it will never get fixed. You should clearly mention the steps to reproduce the bug. Do not assume or skip any reproducing step. Described the issue, step-by-step, so that it is easy to reproduce and fix.
2. **Specific.** Do not write a essay about the problem. Be Specific and to the point. Try to summarize the problem in minimum words yet in effective way. Do not combine multiple problems even they seem to be similar. Write different reports for each problem.

Ensure to include any appropriate log entries from `~/.local/share/qtile/qtile.log` and/or `~/.xsession-errors!`

#### 3.1.2 Writing code

To get started writing code for Qtile, check out our guide to *Hacking on Qtile*.

A more detailed page on creating widgets is available [here](#).

#### Submit a pull request

You've done your hacking and are ready to submit your patch to Qtile. Great! Now it's time to submit a [pull request](#) to our [issue tracker](#) on GitHub.

---

**Important:** Pull requests are not considered complete until they include all of the following:

- **Code** that conforms to PEP8.
  - **Unit tests** that pass locally and in our CI environment (More below).
  - **Documentation** updates on an as needed basis.
- 

Feel free to add your contribution (no matter how small) to the appropriate place in the CHANGELOG as well!

## Unit testing

We must test each *unit* of code to ensure that new changes to the code do not break existing functionality. The framework we use to test Qtile is `pytest`. How `pytest` works is outside of the scope of this documentation, but there are tutorials online that explain how it is used.

Our tests are written inside the `test` folder at the top level of the repository. Reading through these, you can get a feel for the approach we take to test a given unit. Most of the tests involve an object called `manager`. This is the test manager (defined in `test/confstest.py`), which exposes a command client at `manager.c` that we use to test a Qtile instance running in a separate thread as if we were using a command client from within a running Qtile session.

For any Qtile-specific question on testing, feel free to ask on our [issue tracker](#) or on IRC (#qtile on irc.oftc.net).

## Running tests locally

This section gives an overview about `tox` so that you don't have to search [its documentation](#) just to get started. Checks are grouped in so-called `environments`. Some of them are configured to check that the code works (the usual unit test, e.g. `py39`, `pypy3`), others make sure that your code conforms to the style guide (`pep8`, `codestyle`, `mypy`). A third kind of test verifies that the documentation and packaging processes work (`docs`, `docstyle`, `packaging`).

**The following examples show how to run tests locally:**

- To run the functional tests, use `tox -e py39` (or a different environment). You can specify to only run a specific test file or even a specific test within that file with the following commands:

```
tox -e py39 # Run all tests with python 3.9 as the interpreter
tox -e py39 -- -x test/widgets/test_widgetbox.py # run a single file
tox -e py39 -- -x test/widgets/test_widgetbox.py::test_widgetbox_widget
```

- To run style and building checks, use `tox -e docs,packaging,pep8,...`. You can use `-p auto` to run the environments in parallel.

---

**Important:** The CI is configured to run all the environments. Hence it can be time-consuming to make all the tests pass. As stated above, pull requests that don't pass the tests are considered incomplete. Don't forget that this does not only include the functionality, but the style, typing annotations (if necessary) and documentation as well!

---

## 3.2 Hacking on Qtile

### 3.2.1 Requirements

Any reasonably recent version of these should work, so you can probably just install them from your package manager.

- `pytest`
- `Xephyr`
- `xrandr`, `xcalc`, `xeyes` and `xclock` (`x11-apps` on Ubuntu)

On Ubuntu, if testing on Python 3, this can be done with:

```
sudo apt-get install python3-pytest xserver-xephyr x11-apps
```

On ArchLinux, the X11 requirements are installed with:

```
sudo pacman -S xorg-xrandr xorg-xcalc xorg-xeyes xorg-xclock
```

To build the documentation, you will also need to install `graphviz`. On ArchLinux, you can install it with `sudo pacman -S graphviz`.

### 3.2.2 Building cffi module

Qtile ships with a small in-tree pangocairo binding built using cffi, `pangocffi.py`, and also binds to `xcursor` with cffi. The bindings are not built at run time and will have to be generated manually when the code is downloaded or when any changes are made to the cffi library. This can be done by calling:

```
./scripts/ffibuild
```

### 3.2.3 Setting up the environment

In the root of the project, run `./dev.sh`. It will create a virtualenv called `venv`.

Activate this virtualenv with `. venv/bin/activate`. Deactivate it with the `deactivate` command.

### 3.2.4 Building the documentation

Go into the `docs/` directory and run `pip install -r requirements.txt`.

Build the documentation with `make html`.

Check the result by opening `_build/html/index.html` in your browser.

### 3.2.5 Development and testing

In practice, the development cycle looks something like this:

1. make minor code change
2. run appropriate test: `pytest tests/test_module.py` or `pytest -k PATTERN`
3. GOTO 1, until hackage is complete
4. run entire test suite: `pytest`
5. commit

Of course, your patches should also pass the unit tests as well (i.e. `make check`). These will be run by ci on every pull request so you can see whether or not your contribution passes.

### 3.2.6 Coding style

While not all of our code follows [PEP8](#), we do try to adhere to it where possible. All new code should be PEP8 compliant.

The `make lint` command will run a linter with our configuration over libqtile to ensure your patch complies with reasonable formatting constraints. We also request that git commit messages follow the [standard format](#).

### 3.2.7 Deprecation policy

When a widget API is changed, you should deprecate the change using `libqtile.widget.base.deprecated` to warn users, in addition to adding it to the appropriate place in the changelog. We will typically remove deprecated APIs one tag after they are deprecated.

### 3.2.8 Using Xephyr

Qtile has a very extensive test suite, using the Xephyr nested X server. When tests are run, a nested X server with a nested instance of Qtile is fired up, and then tests interact with the Qtile instance through the client API. The fact that we can do this is a great demonstration of just how completely scriptable Qtile is. In fact, Qtile is designed expressly to be scriptable enough to allow unit testing in a nested environment.

The Qtile repo includes a tiny helper script to let you quickly pull up a nested instance of Qtile in Xephyr, using your current configuration. Run it from the top-level of the repository, like this:

```
./scripts/xephyr
```

Change the screen size by setting the `SCREEN_SIZE` environment variable. Default: 800x600. Example:

```
SCREEN_SIZE=1920x1080 ./scripts/xephyr
```

Change the log level by setting the `LOG_LEVEL` environment variable. Default: INFO. Example:

```
LOG_LEVEL=DEBUG ./scripts/xephyr
```

The script will also pass any additional options to Qtile. For example, you can use a specific configuration file like this:

```
./scripts/xephyr -c ~/.config/qtile/other_config.py
```

Once the Xephyr window is running and focused, you can enable capturing the keyboard shortcuts by hitting Control+Shift. Hitting them again will disable the capture and let you use your personal keyboard shortcuts again.

You can close the Xephyr window by enabling the capture of keyboard shortcuts and hit Mod4+Control+Q. Mod4 (or Mod) is usually the Super key (or Windows key). You can also close the Xephyr window by running `qtile cmd-obj -o cmd -f shutdown` in a terminal (from inside the Xephyr window of course).

You don't need to run the Xephyr script in order to run the tests as the test runner will launch its own Xephyr instances.

### 3.2.9 Second X Session

Some users prefer to test Qtile in a second, completely separate X session: Just switch to a new tty and run `startx` normally to use the `~/xinitrc` X startup script.

It's likely though that you want to use a different, customized startup script for testing purposes, for example `~/config/qtile/xinitrc`. You can do so by launching X with:

```
startx ~/config/qtile/xinitrc
```

`startx` deals with multiple X sessions automatically. If you want to use `xinit` instead, you need to first copy `/etc/X11/xinit/xserverrc` to `~/xserverrc`; when launching it, you have to specify a new session number:

```
xinit ~/config/qtile/xinitrc -- :1
```

Examples of custom X startup scripts are available in [qtile-examples](#).

### 3.2.10 Debugging in PyCharm

Make sure to have all the requirements installed and your development environment setup.

PyCharm should automatically detect the `venv` virtualenv when opening the project. If you are using another virtualenv, just instruct PyCharm to use it in `Settings -> Project: qtile -> Project interpreter`.

In the project tree, on the left, right-click on the `libqtile` folder, and click on `Mark Directory as -> Sources Root`.

Next, add a Configuration using a Python template with these fields:

- Script path: `bin/qtile`, or the absolute path to it
- Parameters: `-c libqtile/resources/default_config.py`, or nothing if you want to use your own config file in `~/config/qtile/config.py`
- Environment variables: `PYTHONUNBUFFERED=1;DISPLAY=:1`
- Working directory: the root of the project
- Add contents root to `PYTHONPATH`: yes
- Add source root to `PYTHONPATH`: yes

Then, in a terminal, run:

```
Xephyr +extension RANDR -screen 1920x1040 :1 -ac &
```

Note that we used the same display, `:1`, in both the terminal command and the PyCharm configuration environment variables. Feel free to change the screen size to fit your own screen.

Finally, place your breakpoints in the code and click on `Debug!`

Once you finished debugging, you can close the Xephyr window with `kill PID` (use the `jobs` builtin to get its PID).

### 3.2.11 Debugging in VSCode

Make sure to have all the requirements installed and your development environment setup.

Open the root of the repo in VSCode. If you have created it, VSCode should detect the venv virtualenv, if not, select it.

Create a launch.json file with the following lines.

```
{
 "version": "0.2.0",
 "configurations": [
 {
 "name": "Python: Qtile",
 "type": "python",
 "request": "launch",
 "program": "${workspaceFolder}/bin/qtile",
 "cwd": "${workspaceFolder}",
 "args": ["-c", "libqtile/resources/default_config.py"],
 "console": "integratedTerminal",
 "env": {"PYTHONUNBUFFERED": "1", "DISPLAY": ":1"}
 }
]
}
```

Then, in a terminal, run:

```
Xephyr +extension RANDR -screen 1920x1040 :1 -ac &
```

Note that we used the same display, :1, in both the terminal command and the VSCode configuration environment variables. Then debug usually in VSCode. Feel free to change the screen size to fit your own screen.

### 3.2.12 Resources

Here are a number of resources that may come in handy:

- [Inter-Client Conventions Manual](#)
- [Extended Window Manager Hints](#)
- [A reasonable basic Xlib Manual](#)

### 3.2.13 Troubleshoot

#### Cairo errors

When running the Xephyr script (`./scripts/xephyr`), you might see tracebacks with attribute errors like the following or similar:

```
AttributeError: cffi library 'libcairo.so.2' has no function, constant or global_
↪variable named 'cairo_xcb_surface_create'
```

If it happens, it might be because the `cairocffi` and `xcffib` dependencies were installed in the wrong order.

To fix this:

1. uninstall them from your environment: with `pip uninstall cairocffi xcffib` if using a virtualenv, or with your system package-manager if you installed the development version of Qtile system-wide.
2. re-install them sequentially (again, with `pip` or with your package-manager):

```
pip install xcffib
pip install --no-cache-dir cairocffi
```

See [this issue comment](#) for more information.

If you are using your system package-manager and the issue still happens, the packaging of `cairocffi` might be broken for your distribution. Try to contact the persons responsible for `cairocffi`'s packaging on your distribution, or to install it from the sources with `xcffib` available.

## Fonts errors

When running the test suite or the Xephyr script (`./scripts/xephyr`), you might see errors in the output like the following or similar:

- Xephyr script:

```
xterm: cannot load font "-Misc-Fixed-medium-R-*-13-120-75-75-C-120-IS010646-1"
xterm: cannot load font "-misc-fixed-medium-r-semicondensed--13-120-75-75-c-60-
↪iso10646-1"
```

- pytest:

```
----- Captured stderr call -----
Warning: Cannot convert string "8x13" to type FontStruct
Warning: Unable to load any usable ISO8859 font
Warning: Unable to load any usable ISO8859 font
Error: Aborting: no font found

----- Captured stderr teardown -----
Qtile exited with exitcode: -9
```

If it happens, it might be because you're missing fonts on your system.

On ArchLinux, you can fix this by installing `xorg-fonts-misc`:

```
sudo pacman -S xorg-fonts-misc
```

Try to search for "xorg fonts misc" with your distribution name on the internet to find how to install them.



## MISCELLANEOUS

### 4.1 Frequently Asked Questions

#### 4.1.1 Why the name Qtile?

Users often wonder, why the Q? Does it have something to do with Qt? No. Below is an IRC excerpt where cortesi explains the great trial that ultimately brought Qtile into existence, thanks to the benevolence of the Open Source Gods. Praise be to the OSG!

```
ramnes: what does Qtile mean?
ramnes: what's the Q?
@tych0: ramnes: it doesn't :)
@tych0: cortesi was just looking for the first letter that wasn't registered
 in a domain name with "tile" as a suffix
@tych0: qtile it was :)
cortesi: tych0, dx: we really should have something more compelling to
 explain the name. one day i was swimming at manly beach in sydney,
 where i lived at the time. suddenly, i saw an enormous great white
 right beside me. it went for my leg with massive, gaping jaws, but
 quick as a flash, i thumb-punched it in both eyes. when it reared
 back in agony, i saw that it had a jagged, gnarly scar on its
 stomach... a scar shaped like the letter "Q".
cortesi: while it was distracted, i surfed a wave to shore. i knew that i
 had to dedicate my next open source project to the ocean gods, in
 thanks for my lucky escape. and thus, qtile got its name...
```

#### 4.1.2 When I first start xterm/urxvt/rxvt containing an instance of Vim, I see text and layout corruption. What gives?

Vim is not handling terminal resizes correctly. You can fix the problem by starting your xterm with the “-wf” option, like so:

```
xterm -wf -e vim
```

Alternatively, you can just cycle through your layouts a few times, which usually seems to fix it.

### 4.1.3 How do I know which modifier specification maps to which key?

To see a list of modifier names and their matching keys, use the `xmodmap` command. On my system, the output looks like this:

```
$ xmodmap
xmodmap: up to 3 keys per modifier, (keycodes in parentheses):

shift Shift_L (0x32), Shift_R (0x3e)
lock Caps_Lock (0x9)
control Control_L (0x25), Control_R (0x69)
mod1 Alt_L (0x40), Alt_R (0x6c), Meta_L (0xcd)
mod2 Num_Lock (0x4d)
mod3
mod4 Super_L (0xce), Hyper_L (0xcf)
mod5 ISO_Level3_Shift (0x5c), Mode_switch (0xcb)
```

### 4.1.4 My “pointer mouse cursor” isn’t the one I expect it to be!

Qtile should set the default cursor to `left_ptr`, you must install `xcb-util-cursor` if you want support for themed cursors.

### 4.1.5 LibreOffice menus don’t appear or don’t stay visible

A workaround for problem with the mouse in libreoffice is setting the environment variable `»SAL_USE_VCLPLUGIN=gen«`. It is dependet on your system configuration where to do this. e.g. ArchLinux with `libreoffice-fresh` in `/etc/profile.d/libreoffice-fresh.sh`.

## 4.2 License

This project is distributed under the MIT license.

Copyright (c) 2008, Aldo Cortesi All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## 5.1 How to create a widget

The aim of this page is to explain the main components of Qtile widgets, how they work, and how you can use them to create your own widgets.

---

**Note:** This page is not meant to be an exhaustive summary of everything needed to make a widget.

It is highly recommended that users wishing to create their own widget refer to the source documentation of existing widgets to familiarise themselves with the code.

However, the detail below may prove helpful when read in conjunction with the source code.

---

### 5.1.1 What is a widget?

In Qtile, a widget is a small drawing that is displayed on the user's bar. The widget can display text, images and drawings. In addition, the widget can be configured to update based on timers, hooks, dbus\_events etc. and can also respond to mouse events (clicks, scrolls and hover).

### 5.1.2 Widget base classes

Qtile provides a number of base classes for widgets that can be used to implement commonly required features (e.g. display text).

Your widget should inherit one of these classes. Whichever base class you inherit for your widget, if you override either the `__init__` and/or `_configure` methods, you should make sure that your widget calls the equivalent method from the superclass.

```
class MyCustomWidget(base._TextBox):

 def __init__(self, **config):
 super().__init__("", **config)
 # My widget's initialisation code here
```

The functions of the various base classes are explained further below.

## **\_Widget**

This is the base widget class that defines the core components required for a widget. All other base classes are based off this class.

This is like a blank canvas so you're free to do what you want but you don't have any of the extra functionality provided by the other base classes.

The base `._Widget` class is therefore typically used for widgets that want to draw graphics on the widget as opposed to displaying text.

## **\_TextBox**

The base `._TextBox` class builds on the bare widget and adds a `drawer.TextLayout` which is accessible via the `self.layout` property. The widget will adjust its size to fit the amount of text to be displayed.

Text can be updated via the `self.text` property but note that this does not trigger a redrawing of the widget.

Parameters including `font`, `fontsize`, `fontshadow`, `padding` and `foreground` (font colour) can be configured. It is recommended not to hard-code these parameters as users may wish to have consistency across units.

## **InLoopPollText**

The base `.InLoopPollText` class builds on the base `._TextBox` by adding a timer to periodically refresh the displayed text.

Widgets using this class should override the `poll` method to include a function that returns the required text.

---

**Note:** This loop runs in the event loop so it is important that the `poll` method does not call some blocking function. If this is required, widgets should inherit the base `.ThreadPoolText` class (see below).

---

## **ThreadPoolText**

The base `.ThreadPoolText` class is very similar to the base `.InLoopPollText` class. The key difference is that the `poll` method is run asynchronously and triggers a callback once the function completes. This allows widgets to get text from long-running functions without blocking Qtile.

### **5.1.3 Mixins**

As well as inheriting from one of the base classes above, widgets can also inherit one or more mixins to provide some additional functionality to the widget.

## PaddingMixin

This provides the `padding(_x|_y|)` attributes which can be used to change the appearance of the widget.

If you use this mixin in your widget, you need to add the following line to your `__init__` method:

```
self.add_defaults(base.PaddingMixin.defaults)
```

## MarginMixin

The `MarginMixin` is essentially effectively exactly the same as the `PaddingMixin` but, instead, it provides the `margin(_x|_y|)` attributes.

As above, if you use this mixin in your widget, you need to add the following line to your `__init__` method:

```
self.add_defaults(base.MarginMixin.defaults)
```

## 5.1.4 Configuration

Now you know which class to base your widget on, you need to know how the widget gets configured.

### Defining Parameters

Each widget will likely have a number of parameters that users can change to customise the look and feel and/or behaviour of the widget for their own needs.

The widget should therefore provide the default values of these parameters as a class attribute called `defaults`. The format of this attribute is a list of tuples.

```
defaults = [
 ("parameter_name",
 default_parameter_value,
 "Short text explaining what parameter does")
]
```

Users can override the default value when creating their `config.py` file.

```
MyCustomWidget(parameter_name=updated_value)
```

Once the widget is initialised, these parameters are available at `self.parameter_name`.

### The `__init__` method

Parameters that should not be changed by users can be defined in the `__init__` method.

This method is run when the widgets are initially created. This happens before the `qtile` object is available.

## The `_configure` method

The `_configure` method is called by the `bar` object and sets the `self.bar` and `self.qtile` attributes of the widget. It also creates the `self.drawer` attribute which is necessary for displaying any content.

Once this method has been run, your widget should be ready to display content as the bar will draw once it has finished its configuration.

Calls to methods required to prepare the content for your widget should therefore be made from this method rather than `__init__`.

## 5.1.5 Displaying output

A Qtile widget is just a drawing that is displayed at a certain location the user's bar. The widget's job is therefore to create a small drawing surface that can be placed in the appropriate location on the bar.

### The "draw" method

The `draw` method is called when the widget needs to update its appearance. This can be triggered by the widget itself (e.g. if the content has changed) or by the bar (e.g. if the bar needs to redraw its entire contents).

This method therefore needs to contain all the relevant code to draw the various components that make up the widget. Examples of displaying text, icons and drawings are set out below.

It is important to note that the bar controls the placing of the widget by assigning the `offsetx` value (for horizontal orientations) and `offsety` value (for vertical orientations). Widgets should use this at the end of the `draw` method.

```
self.drawer.draw(offsetx=self.offsetx, width=self.width)
```

---

**Note:** If you need to trigger a redrawing of your widget, you should call `self.draw()` if the width of your widget is unchanged. Otherwise you need to call `self.bar.draw()` as this method means the bar recalculates the position of all widgets.

---

## Displaying text

Text is displayed by using a `drawer.TextLayout` object. If all you are doing is displaying text then it's highly recommended that you use the ``base._TextBox` superclass as this simplifies adding and updating text.

If you wish to implement this manually then you can create a your own `drawer.TextLayout` by using the `self.drawer.textlayout` method of the widget (only available after the `_configure` method has been run). object to include in your widget.

Some additional formatting of Text can be displayed using pango markup and ensuring the `markup` parameter is set to `True`.

```
self.textlayout = self.drawer.textlayout(
 "Text",
 "ffff", # Font colour
 "sans", # Font family
 12, # Font size
 None, # Font shadow
 markup=False, # Pango markup (False by default)
```

(continues on next page)

(continued from previous page)

```
wrap=True # Wrap long lines (True by default)
)
```

## Displaying icons and images

Qtile provides a helper library to convert images to a surface that can be drawn by the widget. If the images are static then you should only load them once when the widget is configured. Given the small size of the bar, this is most commonly used to draw icons but the same method applies to other images.

```
from libqtile import images

def setup_images(self):
 self.surfaces = {}

 # File names to load (will become keys to the `surfaces` dictionary)
 names = (
 "audio-volume-muted",
 "audio-volume-low",
 "audio-volume-medium",
 "audio-volume-high"
)

 d_images = images.Loader(self.imagefolder)(*names) # images.Loader can take more
↳ than one folder as an argument

 for name, img in d_images.items():
 new_height = self.bar.height - 1
 img.resize(height=new_height) # Resize images to fit widget
 self.surfaces[name] = img.pattern # Images added to the `surfaces` dictionary
```

Drawing the image is then just a matter of painting it to the relevant surface:

```
def draw(self):
 self.drawer.ctx.set_source(self.surfaces[img_name]) # Use correct key here for your
↳ image
 self.drawer.ctx.paint()
 self.drawer.draw(offsetx=self.offset, width=self.length)
```

## Drawing shapes

It is possible to draw shapes directly to the widget. The Drawer class (available in your widget after configuration as `self.drawer`) provides some basic functions `rounded_rectangle`, `rounded_fillrect`, `rectangle` and `fillrect`.

In addition, you can access the Cairo context drawing functions via `self.drawer.ctx`.

For example, the following code can draw a wifi icon showing signal strength:

```
import math
```

(continues on next page)

(continued from previous page)

```

...

def to_rads(self, degrees):
 return degrees * math.pi / 180.0

def draw_wifi(self, percentage):

 WIFI_HEIGHT = 12
 WIFI_ARC_DEGREES = 90

 y_margin = (self.bar.height - WIFI_HEIGHT) / 2
 half_arc = WIFI_ARC_DEGREES / 2

 # Draw grey background
 self.drawer.ctx.new_sub_path()
 self.drawer.ctx.move_to(WIFI_HEIGHT, y_margin + WIFI_HEIGHT)
 self.drawer.ctx.arc(WIFI_HEIGHT,
 y_margin + WIFI_HEIGHT,
 WIFI_HEIGHT,
 self.to_rads(270 - half_arc),
 self.to_rads(270 + half_arc))
 self.drawer.set_source_rgb("666666")
 self.drawer.ctx.fill()

 # Draw white section to represent signal strength
 self.drawer.ctx.new_sub_path()
 self.drawer.ctx.move_to(WIFI_HEIGHT, y_margin + WIFI_HEIGHT)
 self.drawer.ctx.arc(WIFI_HEIGHT
 y_margin + WIFI_HEIGHT,
 WIFI_HEIGHT * percentage,
 self.to_rads(270 - half_arc),
 self.to_rads(270 + half_arc))
 self.drawer.set_source_rgb("ffffff")
 self.drawer.ctx.fill()

```

This creates something looking like this:



## Background

At the start of the draw method, the widget should clear the drawer by drawing the background. Usually this is done by including the following line at the start of the method:

```
self.drawer.clear(self.background or self.bar.background)
```

The background can be a single colour or a list of colours which will result in a linear gradient from top to bottom.

## 5.1.6 Updating the widget

Widgets will usually need to update their content periodically. There are numerous ways that this can be done. Some of the most common are summarised below.

### Timers

A non-blocking timer can be called by using the `self.timeout_add` method.

```
self.timeout_add(delay_in_seconds, method_to_call, (method_args))
```

---

**Note:** Consider using the `ThreadPoolText` superclass where you are calling a function repeatedly and displaying its output as text.

---

### Hooks

Qtile has a number of hooks built in which are triggered on certain events.

The `WindowCount` widget is a good example of using hooks to trigger updates. It includes the following method which is run when the widget is configured:

```
from libqtile import hook

...

def _setup_hooks(self):
 hook.subscribe.client_killed(self._win_killed)
 hook.subscribe.client_managed(self._wincount)
 hook.subscribe.current_screen_change(self._wincount)
 hook.subscribe.setgroup(self._wincount)
```

Read the [Built-in Hooks](#) page for details of which hooks are available and which arguments are passed to the callback function.

### Using dbus

Qtile uses `dbus-next` for interacting with dbus.

If you just want to listen for signals then Qtile provides a helper method called `add_signal_receiver` which can subscribe to a signal and trigger a callback whenever that signal is broadcast.

---

**Note:** Qtile uses the `asyncio` based functions of `dbus-next` so your widget must make sure, where necessary, calls to dbus are made via coroutines.

There is a `_config_async` coroutine in the base widget class which can be overridden to provide an entry point for `asyncio` calls in your widget.

---

For example, the `Mpris2` widget uses the following code:

```
from libqtile.utils import add_signal_receiver

...

async def _config_async(self):
 subscribe = await add_signal_receiver(
 self.message, # Callback function
 session_bus=True,
 signal_name="PropertiesChanged",
 bus_name=self.objname,
 path="/org/mpris/MediaPlayer2",
 dbus_interface="org.freedesktop.DBus.Properties")
```

dbus-next can also be used to query properties, call methods etc. on dbus interfaces. Refer to the [dbus-next documentation](#) for more information on how to use the module.

### 5.1.7 Debugging

You can use the `logger` object to record messages in the Qtile log file to help debug your development.

```
from libqtile.log_utils import logger

...

logger.debug("Callback function triggered")
```

---

**Note:** The default log level for the Qtile log is `INFO` so you may either want to change this when debugging or use `logger.info` instead.

Debugging messages should be removed from your code before submitting pull requests.

---

### 5.1.8 Including the widget in `libqtile.widget`

You should include your widget in the `widgets` dict in `libqtile.widget.__init__.py`. The relevant format is `{"ClassName": "modulename"}`.

This has a number of benefits:

- Lazy imports
- Graceful handling of import errors (useful where widget relies on third party modules)
- Inclusion in basic unit testing (see below)

### 5.1.9 Testing

Any new widgets should include an accompanying unit test.

Basic initialisation and configurations (using defaults) will automatically be tested by `test/widgets/test_widget_init_configure.py` if the widget has been included in `libqtile.widget.__init__.py` (see above).

However, where possible, it is strongly encouraged that widgets include additional unit tests that test specific functionality of the widget (e.g. reaction to hooks).

See *Unit testing* for more.

### 5.1.10 Getting help

If you still need help with developing your widget then please submit a question in the [qtile-dev group](#) or submit an issue on the github page if you believe there's an error in the codebase.

- [genindex](#)



## A

addgroup() (*libqtile.hook.subscribe method*), 34  
 AGroupBox (*class in libqtile.widget*), 50

## B

Backlight (*class in libqtile.widget*), 50  
 Bar (*class in libqtile.bar*), 21  
 Battery (*class in libqtile.widget*), 51  
 BatteryIcon (*class in libqtile.widget*), 52  
 BitcoinTicker (*class in libqtile.widget*), 53  
 Bluetooth (*class in libqtile.widget*), 53  
 Bsp (*class in libqtile.layout.bsp*), 38

## C

Canto (*class in libqtile.widget*), 55  
 CapsNumLockIndicator (*class in libqtile.widget*), 56  
 changegroup() (*libqtile.hook.subscribe method*), 34  
 CheckUpdates (*class in libqtile.widget*), 56  
 Chord (*class in libqtile.widget*), 57  
 Click (*class in libqtile.config*), 17  
 client\_focus() (*libqtile.hook.subscribe method*), 34  
 client\_killed() (*libqtile.hook.subscribe method*), 35  
 client\_managed() (*libqtile.hook.subscribe method*), 35  
 client\_mouse\_enter() (*libqtile.hook.subscribe method*), 35  
 client\_name\_updated() (*libqtile.hook.subscribe method*), 35  
 client\_new() (*libqtile.hook.subscribe method*), 35  
 client\_urgent\_hint\_changed() (*libqtile.hook.subscribe method*), 35  
 Clipboard (*class in libqtile.widget*), 57  
 Clock (*class in libqtile.widget*), 58  
 cmd\_add\_rule() (*libqtile.core.manager.Qtile method*), 106  
 cmd\_addgroup() (*libqtile.core.manager.Qtile method*), 106  
 cmd\_bring\_to\_front() (*libqtile.backend.x11.window.Window method*), 113  
 cmd\_change\_vt() (*libqtile.core.manager.Qtile method*), 106

cmd\_commands() (*libqtile.backend.x11.window.Window method*), 113  
 cmd\_commands() (*libqtile.bar.Bar method*), 111  
 cmd\_commands() (*libqtile.config.Screen method*), 112  
 cmd\_commands() (*libqtile.core.manager.Qtile method*), 106  
 cmd\_critical() (*libqtile.core.manager.Qtile method*), 106  
 cmd\_debug() (*libqtile.core.manager.Qtile method*), 107  
 cmd\_delgroup() (*libqtile.core.manager.Qtile method*), 107  
 cmd\_disable\_floating() (*libqtile.backend.x11.window.Window method*), 113  
 cmd\_disable\_fullscreen() (*libqtile.backend.x11.window.Window method*), 113  
 cmd\_display\_kb() (*libqtile.core.manager.Qtile method*), 107  
 cmd\_doc() (*libqtile.backend.x11.window.Window method*), 113  
 cmd\_doc() (*libqtile.bar.Bar method*), 111  
 cmd\_doc() (*libqtile.config.Screen method*), 112  
 cmd\_doc() (*libqtile.core.manager.Qtile method*), 107  
 cmd\_down\_opacity() (*libqtile.backend.x11.window.Window method*), 113  
 cmd\_enable\_floating() (*libqtile.backend.x11.window.Window method*), 113  
 cmd\_enable\_fullscreen() (*libqtile.backend.x11.window.Window method*), 113  
 cmd\_error() (*libqtile.core.manager.Qtile method*), 107  
 cmd\_eval() (*libqtile.backend.x11.window.Window method*), 113  
 cmd\_eval() (*libqtile.bar.Bar method*), 111  
 cmd\_eval() (*libqtile.config.Screen method*), 112  
 cmd\_eval() (*libqtile.core.manager.Qtile method*), 107  
 cmd\_fake\_button\_press() (*libqtile.bar.Bar method*), 111  
 cmd\_findwindow() (*libqtile.core.manager.Qtile method*), 107

`cmd_focus()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_function()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_function()` (*libqtile.bar.Bar method*), 111  
`cmd_function()` (*libqtile.config.Screen method*), 112  
`cmd_function()` (*libqtile.core.manager.Qtile method*), 107  
`cmd_get_position()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_get_size()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_get_state()` (*libqtile.core.manager.Qtile method*), 107  
`cmd_get_test_data()` (*libqtile.core.manager.Qtile method*), 107  
`cmd_groups()` (*libqtile.core.manager.Qtile method*), 107  
`cmd_hide_show_bar()` (*libqtile.core.manager.Qtile method*), 107  
`cmd_hints()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_info()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_info()` (*libqtile.bar.Bar method*), 111  
`cmd_info()` (*libqtile.config.Screen method*), 113  
`cmd_info()` (*libqtile.core.manager.Qtile method*), 107  
`cmd_inspect()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_internal_windows()` (*libqtile.core.manager.Qtile method*), 107  
`cmd_items()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_items()` (*libqtile.bar.Bar method*), 111  
`cmd_items()` (*libqtile.config.Screen method*), 113  
`cmd_items()` (*libqtile.core.manager.Qtile method*), 107  
`cmd_kill()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_labelgroup()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_list_widgets()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_loglevel()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_loglevelname()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_match()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_move_floating()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_next_group()` (*libqtile.config.Screen method*), 113  
`cmd_next_layout()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_next_screen()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_next_urgent()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_opacity()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_pause()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_place()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_prev_group()` (*libqtile.config.Screen method*), 113  
`cmd_prev_layout()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_prev_screen()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_qtile_info()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_qtilecmd()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_reconfigure_screens()` (*libqtile.core.manager.Qtile method*), 108  
`cmd_remove_rule()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_resize()` (*libqtile.config.Screen method*), 113  
`cmd_resize_floating()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_restart()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_run_extension()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_screens()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_set_position()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_set_position_floating()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_set_size_floating()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_shutdown()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_simulate_keypress()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_spawn()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_spawncmd()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_static()` (*libqtile.backend.x11.window.Window method*), 114  
`cmd_status()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_switch_groups()` (*libqtile.core.manager.Qtile method*), 109  
`cmd_switchgroup()` (*libqtile.core.manager.Qtile method*), 110  
`cmd_sync()` (*libqtile.core.manager.Qtile method*), 110

- [cmd\\_to\\_layout\\_index\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[cmd\\_to\\_screen\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[cmd\\_toggle\\_floating\(\)](#) (*libqtile.backend.x11.window.Window method*), 115  
[cmd\\_toggle\\_fullscreen\(\)](#) (*libqtile.backend.x11.window.Window method*), 115  
[cmd\\_toggle\\_group\(\)](#) (*libqtile.config.Screen method*), 113  
[cmd\\_toggle\\_maximize\(\)](#) (*libqtile.backend.x11.window.Window method*), 115  
[cmd\\_toggle\\_minimize\(\)](#) (*libqtile.backend.x11.window.Window method*), 115  
[cmd\\_togglegroup\(\)](#) (*libqtile.config.Screen method*), 113  
[cmd\\_togroup\(\)](#) (*libqtile.backend.x11.window.Window method*), 115  
[cmd\\_togroup\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[cmd\\_toscreen\(\)](#) (*libqtile.backend.x11.window.Window method*), 115  
[cmd\\_tracemalloc\\_dump\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[cmd\\_tracemalloc\\_toggle\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[cmd\\_ungrab\\_all\\_chords\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[cmd\\_ungrab\\_chord\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[cmd\\_up\\_opacity\(\)](#) (*libqtile.backend.x11.window.Window method*), 115  
[cmd\\_validate\\_config\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[cmd\\_warning\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[cmd\\_windows\(\)](#) (*libqtile.core.manager.Qtile method*), 110  
[Cmus](#) (*class in libqtile.widget*), 58  
[Columns](#) (*class in libqtile.layout.columns*), 39  
[CommandSet](#) (*class in libqtile.extension*), 96  
[Countdown](#) (*class in libqtile.widget*), 59  
[CPU](#) (*class in libqtile.widget*), 54  
[CPUGraph](#) (*class in libqtile.widget*), 54  
[current\\_screen\\_change\(\)](#) (*libqtile.hook.subscribe method*), 35  
[CurrentLayout](#) (*class in libqtile.widget*), 60  
[CurrentLayoutIcon](#) (*class in libqtile.widget*), 60  
[CurrentScreen](#) (*class in libqtile.widget*), 61  
**D**  
[delgroup\(\)](#) (*libqtile.hook.subscribe method*), 36  
[DF](#) (*class in libqtile.widget*), 61  
[Dmenu](#) (*class in libqtile.extension*), 97  
[DmenuRun](#) (*class in libqtile.extension*), 97  
[Drag](#) (*class in libqtile.config*), 18  
[DropDown](#) (*class in libqtile.config*), 12  
**E**  
[enter\\_chord\(\)](#) (*libqtile.hook.subscribe method*), 36  
[EzConfig](#) (*class in libqtile.config*), 16  
**F**  
[float\\_change\(\)](#) (*libqtile.hook.subscribe method*), 36  
[Floating](#) (*class in libqtile.layout.floating*), 38  
[focus\\_change\(\)](#) (*libqtile.hook.subscribe method*), 36  
**G**  
[Gap](#) (*class in libqtile.bar*), 21  
[GenPollText](#) (*class in libqtile.widget*), 62  
[GenPollUrl](#) (*class in libqtile.widget*), 62  
[GmailChecker](#) (*class in libqtile.widget*), 63  
[Group](#) (*class in libqtile.config*), 9  
[group\\_window\\_add\(\)](#) (*libqtile.hook.subscribe method*), 36  
[GroupBox](#) (*class in libqtile.widget*), 63  
**H**  
[HDDBusyGraph](#) (*class in libqtile.widget*), 64  
[HDDGraph](#) (*class in libqtile.widget*), 65  
**I**  
[IdleRPG](#) (*class in libqtile.widget*), 65  
[Image](#) (*class in libqtile.widget*), 66  
[ImapWidget](#) (*class in libqtile.widget*), 67  
**J**  
[J4DmenuDesktop](#) (*class in libqtile.extension*), 98  
**K**  
[Key](#) (*class in libqtile.config*), 16  
[KeyboardKbdd](#) (*class in libqtile.widget*), 68  
[KeyboardLayout](#) (*class in libqtile.widget*), 68  
[KeyChord](#) (*class in libqtile.config*), 16  
[KhalCalendar](#) (*class in libqtile.widget*), 69  
**L**  
[LaunchBar](#) (*class in libqtile.widget*), 70  
[layout\\_change\(\)](#) (*libqtile.hook.subscribe method*), 36  
[leave\\_chord\(\)](#) (*libqtile.hook.subscribe method*), 36  
**M**  
[Maildir](#) (*class in libqtile.widget*), 70

Match (class in libqtile.config), 10  
 Matrix (class in libqtile.layout.matrix), 40  
 Max (class in libqtile.layout.max), 40  
 Memory (class in libqtile.widget), 71  
 MemoryGraph (class in libqtile.widget), 72  
 Mirror (class in libqtile.widget), 73  
 Moc (class in libqtile.widget), 73  
 MonadTall (class in libqtile.layout.xmonad), 41  
 MonadWide (class in libqtile.layout.xmonad), 43  
 Mpd2 (class in libqtile.widget), 74  
 Mpris2 (class in libqtile.widget), 77

## N

Net (class in libqtile.widget), 77  
 net\_wm\_icon\_change() (libqtile.hook.subscribe method), 36  
 NetGraph (class in libqtile.widget), 78  
 Notify (class in libqtile.widget), 79  
 NvidiaSensors (class in libqtile.widget), 79

## O

OpenWeather (class in libqtile.widget), 80

## P

Pomodoro (class in libqtile.widget), 82  
 Prompt (class in libqtile.widget), 82

## Q

Qtile (class in libqtile.core.manager), 106  
 QuickExit (class in libqtile.widget), 83

## R

RatioTile (class in libqtile.layout.ratiotile), 45  
 restart() (libqtile.hook.subscribe method), 36  
 Rule (class in libqtile.config), 10  
 RunCommand (class in libqtile.extension), 99

## S

ScratchPad (class in libqtile.config), 11  
 Screen (class in libqtile.config), 21  
 screen\_change() (libqtile.hook.subscribe method), 37  
 selection\_change() (libqtile.hook.subscribe method), 37  
 selection\_notify() (libqtile.hook.subscribe method), 37  
 Sep (class in libqtile.widget), 84  
 setgroup() (libqtile.hook.subscribe method), 37  
 She (class in libqtile.widget), 84  
 shutdown() (libqtile.hook.subscribe method), 37  
 simple\_key\_binder() (in module libqtile.dgroups), 9  
 Slice (class in libqtile.layout.slice), 46  
 Spacer (class in libqtile.widget), 84  
 Stack (class in libqtile.layout.stack), 46

startup() (libqtile.hook.subscribe method), 37  
 startup\_complete() (libqtile.hook.subscribe method), 37  
 startup\_once() (libqtile.hook.subscribe method), 37  
 StockTicker (class in libqtile.widget), 85  
 SwapGraph (class in libqtile.widget), 86  
 Systray (class in libqtile.widget), 86

## T

TaskList (class in libqtile.widget), 87  
 TextBox (class in libqtile.widget), 88  
 ThermalSensor (class in libqtile.widget), 88  
 Tile (class in libqtile.layout.tile), 46  
 TreeTab (class in libqtile.layout.tree), 47

## V

VerticalTile (class in libqtile.layout.verticaltile), 48  
 Volume (class in libqtile.widget), 89

## W

Wallpaper (class in libqtile.widget), 90  
 WidgetBox (class in libqtile.widget), 91  
 Window (class in libqtile.backend.x11.window), 113  
 WindowCount (class in libqtile.widget), 92  
 WindowList (class in libqtile.extension), 99  
 WindowName (class in libqtile.widget), 92  
 WindowTabs (class in libqtile.widget), 93  
 Wlan (class in libqtile.widget), 94  
 Wttr (class in libqtile.widget), 94

## Z

Zoomy (class in libqtile.layout.zoomy), 50